

9.8.6 Create a Guest Network for BYOD

Your Performance

Your Score: 4 of 4 (100%)

Elapsed Time: 4 minutes 31 seconds

Pass Status: **Pass**

Required Score: 100%

Task Summary

Required Actions

- ✓ Create a Guest Access Service [Show Details](#)
- ✓ Create a Guest WLAN [Show Details](#)
- ✓ Request a Guest pass
- ✓ Connect to Guest_BYOD from Gst-Lap

Explanation

Complete this lab as follows:

1. Access and log into the Ruckus **ZoneDirector**.
 - a. From the taskbar, select **Google Chrome**.
 - b. In the URL field, enter **192.168.0.6** and then press **Enter**.
 - c. Maximize the window for easier viewing.
 - d. In the Admin field, enter **admin** (case sensitive).
 - e. In the Password field, enter **password** as the password.
 - f. Select **Login**.
2. Set up Guest Access Services.
 - a. Select the **Configure** tab.
 - b. From the left menu, select **Guest Access**.
 - c. Under Guest Access Service, select **Create New**.
 - d. Change the Name field to **Guest_BYOD**.
 - e. For Terms of Use, select **Show terms of use**.
 - f. Expand **Restricted Subnet Access**.
 - g. Verify that **192.168.0.0/16** is listed.
 - h. Select **OK**.
3. Create a Guest WLAN.
 - a. From the left menu, select **WLANS**.
 - b. Under WLANS, select **Create New**.
 - c. Change the Name to **Guest**.
 - d. Change the ESSID to **Guest_BYOD**.
 - e. Under Type, select **Guest Access**.
 - f. For Wireless Client Isolation, select **Isolate wireless client traffic from other clients on the same AP**.
 - g. Select **OK**.
 - h. Close **Google Chrome**.
4. Request a Guest password.
 - a. Open a new **Google Chrome** browser window.
 - b. In the URL field, enter **192.168.0.6/guestpass** and then press **Enter**.
 - c. Maximize the window for easier viewing.
 - d. In the Username field, enter **BYODAdmin** (case sensitive).
 - e. Enter **P@ssw0rd** as the password (0 is a zero).

- f. Select **Log In**.
 - g. In the Full Name field, enter any *full name*.
 - h. In the Key field, highlight the **key** and press **Ctrl + C** to copy the key.
 - i. Select **Next**.
5. Access the wireless Guest Access Service from the guest laptop in the lobby.
- a. From the top menu, select **Floor 1**.
 - b. Select **Gst-Lap** in the lobby.
 - c. In the notification area, select the **Network** icon.
 - d. Select **Guest_BYOD**.
 - e. Select **Connect**.
 - f. Select **Yes**.
 - g. After Internet Explorer opens to the Guest Access login page, paste the **key** from the Key field.
 - h. Select **Log In**.

Copyright © 2022 TestOut Corporation All rights reserved.