

### 11.3.5 Implement Intrusion Prevention

## Your Performance

Your Score: 5 of 5 (100%)

Pass Status: **Pass**

Elapsed Time: 2 minutes 14 seconds

Required Score: 100%

## Task Summary

### Required Actions

- ✓ Configure Snort rules [Hide Details](#)

- + Enable Snort VRT
- + Enter the Snort Oinkmaster Code of 359d00c0e75a37a4dbd70757745c5c5dg85aa
- + Enable Snort GPLv2
- + Enable ET Open

- ✓ Configure Sourcefire OpenAppID Detectors [Hide Details](#)

- + Enable OpenAppID
- + Enable RULES OpenAppID

- ✓ Configure the Rules Update Settings [Hide Details](#)

- + Use the Update Interval of 1 Day
- + Use an Update Start Time of 01:00
- + Hide Deprecated Rules Categories

- ✓ Configure General Settings [Hide Details](#)

- + Use the Remove Blocked Hosts Interval of 1 HOUR
- + Enable Startup/Shutdown Logging

- ✓ Configure the Snort Interface settings for the WAN interface [Hide Details](#)

- + WAN interface is enabled
- + Description: WANSnort
- + Send Alerts to System Log enabled
- + Block offenders enabled
- + Snort started on the WAN interface

## Explanation

Complete this lab as follows:

1. Sign into the pfSense management console.
  - a. In the Username field, enter **admin**.
  - b. In the Password field, enter **P@ssw0rd** (zero).
  - c. Select **SIGN IN** or press **Enter**.
2. Access the Snort Global Settings.

- a. From the pfSense menu bar, select **Services > Snort**.
- b. Under the Services breadcrumb, select **Global Settings**.
3. Configure the required rules to be downloaded.
  - a. Select **Enable Snort VRT**.
  - b. In the *Sort Oinkmaster Code* field, enter **359d00c0e75a37a4dbd70757745c5c5dg85aa**. You can copy and paste this from the scenario.
  - c. Select **Enable Snort GPLv2**.
  - d. Select **Enable ET Open**.
4. Configure the Sourcefire OpenAppID Detectors to be downloaded.
  - a. Under Sourcefire OpenAppID Detectors, select **Enable OpenAppID**.
  - b. Select **Enable RULES OpenAppID**.
5. Configure when and how often the rules will be updated.
  - a. Under Rules Update Settings, use the Update Interval drop-down menu to select **1 Day**.
  - b. For Update Start Time, change to **01:00**.
  - c. Select **Hide Deprecated Rules Categories**.
6. Configure Snort General Settings.
  - a. Under General Settings, use the Remove Blocked Hosts Interval drop-down menu to select **1 HOUR**.
  - b. Select **Startup/Shutdown Logging**.
  - c. Select **Save**.
7. Configure the Snort Interface settings for the WAN interface.
  - a. Under the Services breadcrumb, select **Snort Interfaces** and then select **Add**.
  - b. Under General Settings, make sure **Enable interface** is selected.
  - c. For Interface, use the drop-down menu to select **WAN (PFSense port 1)**.
  - d. For Description, use **WANSnort**.
  - e. Under Alert Settings, select **Send Alerts to System Log**.
  - f. Select **Block Offenders**.
  - g. Scroll to the bottom and select **Save**.
8. Start Snort on the WAN interface.
  - a. Under the Snort Status column, select the **arrow**.
  - b. Wait for a checkmark to appear, indicating that Snort was started successfully.

---

Copyright © 2022 TestOut Corporation All rights reserved.