Starting bitcoin core

Configuration

```
590424-0014:~$ cat ~/.bitcoin/bitcoin.conf
# Enable server mode
server=1
# Enable transaction indexing (useful for Electrum server)
# Run in the background
daemon=1
# Enable Signet network
signet=1
# Default RPC settings for Signet
rpcport=38332
rpcbind=0.0.0.0
rpcallowip=127.0.0.1
rpcallowip=192.0.0.0/16
# Configuration générale pour les connexions et la sécurité
proxy=127.0.0.1:9050
listen=1
whitelist=127.0.0.1
# Restrict network types to IPv4, IPv6, and Onion (Tor)
onlynet=ipv4
onlynet=onion
# RPC authentication (do not share this publicly)
rpcauth=Dwayne67E:62de6d173b2fa8e0f85c60473442198c$a560f20e6cd1674725c1bdeb1bc87a1dcd567b5ac449b86bab87918455ba1707
# ZMQ settings for real-time block and transaction updates
zmqpubrawblock=tcp://0.0.0.0:28332
zmqpubrawtx=tcp://0.0.0.0:28333
zmqpubhashblock=tcp://0.0.0.0:28334
# Section spécifique au réseau Signet
[signet]
rpcuser=Dwayne67E
rpcpassword=playboy
rpcport=18332
rpcbind=0.0.0.0
# Addnodes to connect to for the Signet network
addnode=178.128.221.177:38333
addnode=2604:a880:400:d0::16b:c001:38333
```

Setup RPC Authentification

```
administrateurl@MESIFI590424-0014:~/downloads$ ./rpcauth.py admin admin String to be appended to bitcoin.conf: rpcauth=admin:b0ad908ab1b0a0887c067a42af4c44dd$40c45fabdaa2fc058a47f3f62a521a44890e56f7631817b72 2f6fa0da6184667 Your password: admin
```

Setup Tor

```
administrateur1@MESIFI590424-0014:~/downloads$ sudo apt install tor Reading package lists... Done Building dependency tree... Done Reading state information... Done tor is already the newest version (0.4.6.10-1). 0 upgraded, 0 newly installed, 0 to remove and 10 not upgraded.
```