SI unit of heat capacity is J/K. It is also expressed in cal/°C, kcal/°C or J/°C.

**Problem 4**

An iron ball requires 5000 J heat energy to raise its temperature by 20 K. Calculate the heat capacity of the iron ball.

**Solution:**

Given, $Q = 5000$ J, $\Delta T = 20$ K

$$\text{Heat Capacity, } C = \frac{\text{Heat energy required, } Q}{\text{Rise in temperature, } \Delta T}$$

$$= \frac{5000}{20} = 250 \text{ JK}^{-1}$$

## 7.5 Change of state

The process of changing of a substance from one physical state to another at a definite temperature is known as change of state.

For example, water molecules are in liquid state at normal temperature. When water is heated to 100°C, it becomes steam which is a gaseous state of matter. On reducing the temperature of the steam it becomes water again. If we reduce the temperature further to 0 °C, it becomes ice which is a solid state of water. Ice on heating, becomes water again. Thus, water changes its state when there is a change in temperature. There are different such processes in the change of state in matter. Figure 7.8 shows various processes of change of state.





**Figure 7.8** Change of state of matter

**Melting – Freezing**

The process in which a solid is converted to liquid by absorbing heat is called melting or fusion. The temperature at which a solid changes its state to liquid is called melting point. The reverse of melting is freezing. The process in which a liquid is converted to solid by releasing heat is called freezing. The temperature at which a liquid changes its state to solid is called freezing point. In the case of water, melting and freezing occur at 0°C.

**Boiling-Condensation**

The process in which a liquid is converted to vapor by absorbing heat is called boiling or vaporization. The temperature at which a liquid changes its state to gas is called boiling point. The process in which a vapor is converted to liquid by releasing heat is called condensation. The temperature at which vapour changes its state to liquid is called condensation point. Boiling point as well as condensation point of water is 100°C.

**Sublimation**

Some solids like dry ice, iodine, frozen carbon dioxide and naphthalene balls change directly from solid state to gaseous state without becoming liquid. The process in which a solid is converted to gaseous state is called sublimation.

Various stages of conversion of state of matter by heat with the corresponding change in temperature is shown in Figure 7.9





**Figure 7.9** Various stages of conversion of state of matter

## 7.6 Latent heat

The word, 'latent' means hidden. So, latent heat means hidden heat or hidden energy. In order to understand latent heat, let us do the activity given below.



IX_SCI_EM_Unit-07_PHY.indd 86 12/7/2022 6:13:32 PM