

Table of Contents

- Storage system
 - Storage overview
 - BeeGFS storage policy
 - BeeGFS external access

Previous topic

[Working on OWL](#)

This Page

[Show Source](#)

Quick search

Storage system

Storage overview

The OWL system is connected with several storage servers. Most important is the BeeGFS storage system that provides the users and project directories. The user directories (mounted at /bg/home) should be used for account configuration, scripts, etc.; however, simulation input or results should be stored in a project directory. These are located in /bg/data. In addition, a flash-based storage exists for data that needs quicker read/write access, or trees with many small files, e.g., python environments. The general net-drives (transfer, project and group directories, rawdata) are available in /netapp. Until it's decommissioning, the GPFS storage with old project directories is still available at the /pd mountpoint.

The current state of the individual quota can be queried using the **bgquota** command. It can be queried for any project directory by supplying its directory name as argument, (e.g., bgquota climate_data).

OWL network mounts overview			
mount point	pointing to		file system
/bg/home	BeeGFS Home		BeeGFS native
/bg/fast	BeeGFS storage	SSD	BeeGFS native
/bg/data	BeeGFS projects		BeeGFS native
/pd/data	GPFS projects		nfs4 (read only)
/transfer	Central directory (T)	transfer	nfs4
/netapp/data	Central directory (G)	group	nfs4
/netapp/archive	Central directory	archive	nfs4
/netapp/rawdata	Central directory	raw data	nfs4

BeeGFS storage policy

On the BeeGFS, every user gets a 100GB space in /bg/home. Project directories can be requested from me. Please send me a message (Mattermost) with project name, responsible person, suggested duration, amount of required space and a list of user-ids that should have access to the project's data.

Two directories provide data for all users: 1) /bg/data/**modelinput** for common model input data, such as, e.g., data for the WRF preprocessing tool, or reanalysis data; 2) /bg/data/**climate_data** for common data-sets like, e.g., gridded precipitation or temperature fields, etc.

Disk quota are mapped to specific BeeGFS user groups. Each project directory gets a common group named **g_bgfs_data_[project]** and each user gets a group named **g_bgfs_usr_[user-n]**. These group settings are automatically inherited for all project directories and their subtrees. Data are by default read/write accessible by owners and members of the project group and hidden for all other users. Thus if you want someone to access your data, the person should be added to the respective user group (which requires a message to me).

BeeGFS external access

The BeeGFS mounts are in general accessible from your computers via NFS. Please ask your (AI) search-engine about how to connect these in your OS.

```
owl01amd.imk-ifu.kit.edu:/data /bg/data nfs
rw,timeo=60,retrans=32,hard,intr,bg 0 0
owl01amd.imk-ifu.kit.edu:/bg /bg nfs
rw,timeo=60,retrans=32,hard,intr,bg 0 0
```