

Media button

Control audio and video playback.

- Overview
- Specs

States

Media buttons come in five states: default, hover, focus, pressed, and disabled. To learn more about each interaction state, visit the [button guidelines](#).

onLite

onHeavy and onPhoto

onPhoto

	Default	Hover	Focus	Pressed	Disabled
Primary					
Secondary					

Size

Media buttons come in three sizes: small, medium and large.


Small

Medium

Large


Size	Usage	Dimensions	Target size	Icon size
Small	Where there is limited space.	38×38px	38×38px	

Size	Usage	Dimensions	Target size	Icon size
Medium	Default button.	48×48px	48×48px	
Large	In larger components, such as heroes.	56×56px	56×56px	




⊗ Don't

Don't change the proportions of the buttons.



⊗ Don't

Don't use differently sized buttons in the same group.



⊗ Don't

Don't use an outlined icon for primary actions.

Color

onLite

Primary

Default



#1d365a



#ffffff

Action Primary Default onLite



#ffffff



#171a22

Text Inverse

Hover



#121a38



#c7ccd3

Action Primary Hover onLite



#ffffff



#171a22

Text Inverse

Focus



#1d365a



#ffffff

Action Primary Default onLite



#ffffff



#171a22

Text Inverse



#2e323a




#ffffff

Action Focus onLite

Pressed



#070a16



#e9edf3

Action Primary Pressed onLite



#ffffff



#171a22

Text Inverse

Disabled




#a6acb5



#3c414a

Action Disabled



#d9dde3



#a6acb5

Action Disabled Content

Secondary

Default



#1d365a




#ffffff

Action Primary Default onLite

Hover



#121a38



#c7ccd3

Action Primary Hover onLite

Focus



#1d365a



#ffffff

Action Primary Default onLite



#2e323a




#ffffff

Action Focus onLite

Pressed



#070a16



#e9edf3

Action Primary Pressed onLite

Disabled



#a6acb5



#3c414a

Action Disabled

> onHeavy and onPhoto

> onPhoto

Color guidelines



 Don't

Don't change color of the buttons.



 Don't

Don't use the onPhoto variant for light backgrounds. Use the onLite variant instead.




 Don't

Don't use the primary onLite variant on video.



 Do

Use onPhoto variants on videos.



Listen to Jonathan Smith

Solution architect

Client story









00:00

00:46

1x

 Don't

Don't use the onPhoto variant for light backgrounds. Use the onLite variant instead.



Media button
Overview

Menu button
Overview

