


Media button

Control audio and video playback.

- Overview
- Specs


States

Media buttons come in five states: default, hover, focus, pressed, and disabled. To learn more about each interaction state, visit the [button guidelines](#).




Size

Media buttons come in three sizes: small, medium and large.




Size	Usage	Dimensions	Target size	Icon size
Small	Where there is limited space.	38×38px	38×38px	S
Medium	Default button.	48×48px	48×48px	M

Size	Usage	Dimensions	Target size	Icon size
Large	In larger components, such as heroes.	56×56px	56×56px	




⊗ Don't

Don't change the proportions of the buttons.



⊗ Don't

Don't use differently sized buttons in the same group.



⊗ Don't

Don't use an outlined icon for primary actions.

Color

> onLite

> onHeavy and onPhoto

▼ onPhoto

Secondary

Default


#ffffff


#ffffff

Action Primary Default onHeavy


rgba(0,0,0,0)


rgba(0,0,0,0)

Action Primary Default onPhoto

Hover



#f4f6f9



#c7ccd3

Action Primary Hover onHeavy



#171a22



#171a22

Text Always Black

Focus



#ffffff



#ffffff

Action Focus onHeavy



#ffffff



#ffffff

Action Primary Default onHeavy




rgba(0,0,0,0)




rgba(0,0,0,0)

Action Primary Default onPhoto

Pressed



#e9edf3



#e9edf3

Action Primary Pressed onHeavy



#171a22



#171a22

Text Always Black

Disabled




#a6acb5



#3c414a

Action Disabled



#d9dde3



#a6acb5

Color guidelines



⊗ Don't

Don't change color of the buttons.



⊗ Don't

Don't use the onPhoto variant for light backgrounds. Use the onLite variant instead.




⊗ Don't

Don't use the primary onLite variant on video.




✓ Do

Use onPhoto variants on videos.



Listen to Jonathan Smith
Solution architect

Client story



1x

00:00

00:46

⊗ Don't

Don't use the onPhoto variant for light backgrounds. Use the onLite variant instead.



Media button
Overview

Menu button
Overview

