

Notice

Provide brief, contextual feedback or updates to users.

Properties

Property	Values	Default
Category Variant	Warning Success Information	Warning
Show time Boolean	true false	true
Show subtitle Boolean	true false	true
Close icon Boolean	true false	true

Size

The minimum width of the notice is 312px.

Used components sizes

These are the sizes of components that are used in the notice.

Element	Desktop	Desktop small	Tablet large	Tablet	Mobile
Icon	S	S	S	S	S

Typography


Element	Desktop	Desktop small	Tablet large	Tablet	Mobile
Headline	heading-2xs-400-regular	heading-2xs-400-regular	heading-2xs-400-regular	heading-2xs-400-regular	heading-2xs-400-regular
Subtitle	heading-2xs-300-light	heading-2xs-300-light	heading-2xs-300-light	heading-2xs-300-light	heading-2xs-300-light
Time	body-xs-400-regular	body-xs-400-regular	body-xs-400-regular	body-xs-400-regular	body-xs-400-regular

Viewport

Notice is available in a single size to be used in all viewports.

Placement

Notice can be placed at the top corner of the interface when it is used as a temporary message box that pops up on the screen to give the user feedback.



Desktop and mobile placement examples.

×

Get in touch

We combine strategy, technology, and creativity to guide organizations through complex challenges, unlock new opportunities.

* Mandatory fields

First name*

Email address*

ⓘ

Error experienced

You need to accept the terms & conditions to continue.

☐ I agree to Capgemini collecting and processing my personal data to allow me to receive information on Capgemini services. For further information, please see [our Privacy Notice](#).


Send

The notice can also be placed within a form, modal or popup when it is used as an error message, callout or information that isn’t temporary (doesn’t disappear and cannot be closed by user) and requires the user’s action.

Notice within a form.

Character limit


The text in the notice is limited to four lines in total (two lines for the title and two lines for the subtitle). The exact character limit depends on the component width.



Example of the maximum amount of lines

Color

Error Success Information



Surface Cloud Lite



Text Primary



Action Active



Notice
Overview

Notice Guidelines

