


Switch

Offers a binary choice.

Overview Specs Guidelines


States

Light mode Dark mode



1. **Default:** Appears when the switch is enabled but not currently interacted with.
2. **Hover:** Triggers when the user’s pointer moves over the switch. This state provides a visual cue that the element is interactive.
3. **Keyboard focus:** Appears when the button is selected via keyboard navigation (e.g. using the Tab key), indicating it is ready for interaction.
4. **Pressed:** Activates when the switch is being pressed or tapped.
5. **Disabled.** Represents an inactive switch that cannot be selected or focused. This state is used when the option is unavailable due to system rules or user permissions.

Size



Switches are available in two sizes: small and large.

Small switches are suited for compact interfaces such as filter groups, or mobile layouts. They are ideal for dense UI sections where multiple options are presented in a limited area.

Large switches are recommended for spacious layouts, like preference panels and selection cards. The increased size helps users identify and select options more easily, especially on touch devices or larger screens.

Size	Usage	Dimensions	Target height
Small	Used in compact layouts with limited space.	40×32px	40×40px
Large	Used in spacious layouts where options need emphasis.	56×32px	56×32px

Interaction

- Users can activate a switch by clicking either the switch itself or its associated label.
- Both the switch and label should respond to pointer events. When hovering over this region, the cursor must change to a pointer to indicate that the element is clickable.

Switch groups

Placement

The switch may be used in groups of several switches or in conjunction with other input items.

Align lists of switches to the left for and if needed, organize them into multiple columns.

Privacy

☒ Show photo

☐ Share location

Notifications

☐ Email alerts

☐ Push notifications

✖ Don't

Don't place switches horizontally in rows.

Privacy

☒ Show photo

☐ Share location

☐ Display status

Notifications

☐ Email alerts

☐ Push notifications

☐ Play sound

✔ Do

Place switches next to each other in columns.

Spacing

When grouped together, switches should have the `spacing-xs token` (16px) applied as [spacing](#) between them. Always ensure there is consistent spacing between each switch in the group.

Group label

☐ Label

☒ Label

☐ Label

16px

16px

16px

Color

✔ Do

✔

Send notifications

✕

Show settings

Use the default styling.

✕ Don't

✔

Send notifications

✕

Show settings

Don't change the styling of the switch.