#### Overview Package Class Use Tree Deprecated Index Help

SUMMARY: NESTED | FIELD | CONSTR | METHOD

FRAMES NO FRAMES All Classes DETAIL: FIELD | CONSTR | METHOD

org. apache. commons. pool2. impl

## Class DefaultEvictionPolicy<T>

java. lang. Object

└org. apache. commons. pool2. impl. DefaultEvictionPolicy<T>

Type Parameters:

T - the type of objects in the pool

All Implemented Interfaces:

EvictionPolicv<T>

public class DefaultEvictionPolicy(T> 提供用于对象池的"驱逐策略(EvictionPolicy)"的默认实现

extends Object

implements EvictionPolicy<T>

如果满足以下条件,空闲池对象将被驱逐:

Provides the default implementation of EvictionPolicy used by the pools. Objects will be evicted if the following conditions are met: 池对象的空闲时间超过minEvictableIdleTime

• the object has been idle longer than GenericObjectPool.getMinEvictableIdleTimeMillis() / GenericKeyedObjectPool.getMinEvictableIdleTimeMillis()

 there are more than GenericObjectPool.getMinIdle() / GenericKeyedObjectPoolConfig.getMinIdlePerKey() idle objects in the pool and the object has been idle for longer than GenericObjectPool.getSoftMinEvictableIdleTimeMillis() / 对象池中的空闲对象数超过minIdle,且池对象的 GenericKeyedObjectPool.getSoftMinEvictableIdleTimeMillis() 空闲时间超过softMinEvictableIdleTime

此类是不可变和线程安全的 This class is immutable and thread-safe.

Since:

2.0

Version:

\$Revision: \$

# Constructor Summary

DefaultEvictionPolicy()

### Method Summary

boolean evict(EvictionConfig config, PooledObject<T> underTest, int idleCount)

This method is called to test if an idle object in the pool should be evicted or not.

Methods inherited from class java. lang. Object

clone, equals, finalize, getClass, hashCode, notify, notifyAll, toString, wait, wait, wait

### Constructor Detail

DefaultEvictionPolicy

public DefaultEvictionPolicy()

### Method Detail

evict

public boolean evict(EvictionConfig config, PooledObject<T> underTest,

2015/1/25 21:04

int idleCount)

Description copied from interface: EvictionPolicy

This method is called to test if an idle object in the pool should be evicted or not.

Specified by:

evict in interface EvictionPolicy<T>

Parameters:

config - The pool configuration settings related to eviction

 $under Test\ \hbox{--} The\ pooled\ object\ being\ tested\ for\ eviction$ 

idleCount - The current number of idle objects in the pool including the object under test

Returns:

true if the object should be evicted, otherwise false

Overview Package Class Use Tree Deprecated Index Help

PREV CLASS NEXT CLASS
SUMMARY: NESTED | FIELD | CONSTR | METHOD

FRAMES NO FRAMES All Classes
DETAIL: FIELD | CONSTR | METHOD

Copyright © 2001 - 2014 The Apache Software Foundation. All rights reserved.