11/07

First day → First evaluation day
part 3 — second planting day

Time	Activity	Notes
14:35	Set Gc to 80% RH	15:30 in GC hours.
08:20	watered the plants	
Gc clock		
09:55	09:02 changed °T to 32°C	
10:24	09:30 set to 82% RH	
10:43	09:50 → 35 Start T1 (31,9°C / 76%)	weighted pots
11:18	10:25 Finish T1	weighted pots
11:19	10:25 Set Gc to 68% RH	28 / 81 min
11:46	10:53 → 48 Start T2 (32,1, 70%)	
12:35	11:41 Finish T2	weighted pots → 45min
12:36	11:43 Set to 58%	16 min
12:51	11:58 → 35 Start T3	12:06 Finish T3 (weighted pots)
13:28	12:39 Set Gc to 42%	1 hour
	13:03 Set Gc to 40%	
14:34	13:27 → 35 Start T4 (42,32,2°C)	14:07 Finish T4
16:09	14:02 Set Gc to 25% RH	→ weighted pots
15:15	14:21 Set Gc to 15% RH	
15:26	14:33 → 35 Start T5	15:08 Finish T5
16:02		
16:19	15:25 change back to 80%	watered plants
16:28	15:39 back T°C to 28°C	

T1 → 28 min
T2 → 16 min
T3 → 1 hour (66)
T4 → 17 min
T5

- (9:50 → 10:25)
- (10:53 → 11:41)
- (11:51 → 12:26)
- (13:27 → 14:02)
- (14:33 → 15:08)

T1 → 28 min
T2 → 16 min
T3 → 66
T4 → 17 min
T5

não estou considerando esse intervalo entre T, só início e final

T4 = 1,0

→ Se considerar o tempo de pesagem = gap VPD

T1 → 10:43 - 11:18
T2 → 11:18 → 11:53
T3 → 12:35 → 13:10
T4 → 13:26 → 14:01
T5 → 15:09 → 15:44

não tenho

→ tempo pesagem = início próximo T.

→ set Gc to RH target
→ weight all the pots
→ wait the Gc stabilize according to the VPD targets
→ when stabilizes → start the treatment → take notes about the time
→ wait 35 minutes
→ Finish treatment → weight pots
→ change Gc set up.

{T2 → tratamento das reuniões → dura mais}

Treatment

Time to start stabilizing: 15 minutes

→ Set the GC → weigh pots → wait stabilizing → start Treatment

second evaluation day
part 3 - 11/08 second planting date

GC time	Time	Activity	Notes
08:54	08:01	set GC to 32°C	
	07:50	unshaved plants	
09:19	08:26	set GC to 82% RH	
	08:50	weighted pots	
09:50	08:56	start T1 (31.7°C / 78% RH)	
	09:31	Finish T1	
10:24	09:31	set up GC to 68% RH	
		weighted pots →	End T1
	10:01	weight pots (beg. T2)	
10:58	10:05	start T2 (31.7°C / 66% RH)	
	10:40	Finish T2	
11:33	10:40	set up GC to 66% RH	
		weighted pots (end T2)	
	11:10	weight pots (beg T3)	
12:09	11:15	Start T3 (31.6°C / 55% RH)	
	11:50	Finish T3	
12:44	11:50	set up GC to 44% RH	12:10 (GC 13:04) set to 40% RH
		weighted pots (end T3)	
	12:20	weight pots (beg T4)	
13:20	12:26	start T4 (31.7°C / 44% RH)	
	13:01	Finish T4	
13:55	13:01	set up to 15% RH	
		weighted pots (end T4)	
	13:31	weight pots (beg T5)	
14:33	13:39	start T5 (27% RH, 32.3°C)	
15:07	14:14	Finish T5	

Order:

Set up treatment → wait 30 min (stabilize) → weight pots → start treatment (35 min)