


June ^{2nd}.,2018 Course Code: CSE 345&347 Time: 3 Hours

Real-Time and Embedded Systems Design

ورق الأسئلة هو كراسة الأجابة _ لابد من تدبيس ورق الأسئلة مع غلاف بيانات الطالب (Solve in Designated Area - Assume Any Missing Data if Any)

Question (1):(5 Marks)



After each clock pulse, decide what are in the blocks A, B, and C, like values or decisions. "A" has the digital SAR value. "B" is the DAC output value in Volt. "C" could be "GT" (+ve > -ve) and "LT" otherwise. Fill your answer in the following table.

	A	В	C
After Clock Pulse 1			
After Clock Pulse 2			
After Clock Pulse 3			
After Clock Pulse 4			
After Clock Pulse 5			
After Clock Pulse 6			
After Clock Pulse 7			
After Clock Pulse 8			

Sherif Hammad P.T.O





June ^{2nd.} ,2018	Course Code: CSE 345&347	Time: 3 Hours
D 170°	1E 1 11 10 (B :	

Real-Time and Embedded Systems Design

Question (2): (6 Marks)

The Figure below shows the example of configuration of Sample Sequencer 1 and Sample Sequencer 3. Complete the following C-Snippet to achieve this purpose. Few comments are only given. Do your best to recall TIVA-Ware APIs, arguments and necessary constants definitions.





Sherif Hammad P.T.O



June ^{2nd}. 2018 Time: 3 Hours Course Code: CSE 345&347 **Real-Time and Embedded Systems Design**

The Exam Consists of <u>6</u> Questions in <u>6</u> Pages Total Marks: 40 Marks 3/6

Question (3): (5 Marks)

	CIRCLE THE CORRECT ANSWER
1.	The number of bytes per I2C transfer is defined as the time period between a valid
	and condition and is unrestricted, but each data byte has to be followed by an
	acknowledge bit, and data must be transferred first.
	a) START, LSB, STOP
	b) STOP, START, MSB
	c) LSB, START, STOP
	d) START, STOP, MSB
2.	In each I2C module, after the START condition, a slave address is first transmitted. This address
	is bits long followed by a bit.
	a) 8, START
	b) 8, STOP
	c) 7, R/S
	d) 8, R/S

- 3. If a slave is servicing an internal interrupt, which of the following will it do to avoid losing data?
 - a) Terminate the interrupt.
 - b) Stop the clock and reset the system.
 - c) Stretch the clock until the interrupt servicing is complete.
 - d) Stop servicing the interrupt and get the data from the bus.
 - e) Turn itself into the bus master
- 4. When must data be stable for a correct I²C bus transaction?
 - a) When the clock is low
 - b) When the clock is in high-impedance state
 - c) When the clock transitions high to low
 - d) When the clock is high
 - e) When the clock transitions low to high
 - f) Anytime is acceptable
- 5. The I²C bus can connect several devices at the same time to its clock and data lines in a wired-AND format. Which kind of outputs must a device have to operate on the I²C bus?
 - a) Tri-state
 - b) Open collector
 - c) Emitter follower
 - d) Source follower
 - e) Open drain
 - f) a and c only
 - g) b and e only

Sherif Hammad P.T.O



June ^{2nd}. 2018 Course Code: CSE 345&347 Time: 3 Hours

Real-Time and Embedded Systems Design

The Exam Consists of **6** Questions in **6** Pages Total Marks: 40 Marks

4/6

Question (4):(8 Marks)

The figure below is a snap shot from a debugging session. In the following table, document your expectation of the hitting-order of Breakpoints (designated by line number). Consider multiple hits of a break point, inside a loop, as ONLY 1 HIT.

```
63
                            int main ( void )
                       64 □ {
                              иМитен = иSemaphoreCreateMuten();
                       65
                       66
                              if ( mbfwben !- NULL )
                       67 😑
                                 gTaskCreate( prvPrintTask, "Print1", 240, "Task 1 **\n", 1, NULL );
                       68
                                #TaskCreate( prvPrintTask, "Print2", 240, "Task 2 --\n", 2, NULL );
                       69
                       70
                                 vTaskStartScheduler();
                       71
                              1
                       72 []
                       72
                            static void prvNewPrintString( const portCHAR *pcString )
                       74 🖵 (
                       75
                            static char cBuffer[ mainMAX MSG LEN ];
                       76
                            int i,j;
                       77
                              иSemaphoreTake ( иМитем, portMAX_DELAY );
Breakpoint 77
                       78 🖨
Breakpoint 79
                       79
                                sprintf( cBuffer, "%s", pcString );
                       80
                                 for (i=1;i<1000000;i++)
                       81 |
Breakpoint 82
                       82
                                  j++;
                       83
Breakpoint 84
                       84
                                printf( cBuffer );
                       85
Breakpoint 86
                       86
                              nSemaphoreGive ( nMuten );
                       87
                       88
                            static void prvPrintTask( void *pvParameters )
                       89 🗇 (
                       90
                            char *pcStringToPrint;
                       91
                            int i,j;
                       92
                              pcStringToPrint = ( char * ) pvParameters;
                       93
                              for( ;; )
                       94 🖨
Breakpoint 95
                                prvNewPrintString( pcStringToPrint );
                       95
                                 for (i=1;i<1000000;i++)
                       96
                       97 🖨
Breakpoint 98
                       98
                                  j++;
                       99
                      100
                                vTaskDelay( 255 );
Breakpoint 100
                      101
                           L
                      102
```

Hit Order	Break Point No.	Hit Order	Break Point No.	Hit Order	Break Point No.
1		11		21	
2		12		22	
3		13		23	
4		14		24	
5		15		25	
6		16		26	
7		17		27	
8		18		28	
9		19		29	
10		20		30	

Sherif Hammad P.T.O



June 2nd., 2018 Course Code: CSE 345&347 Time: 3 Hours

Real-Time and Embedded Systems Design

The Exam Consists of **6** Questions in **6** Pages Total Marks: 40 Marks 5/6

Question (5): (8 Marks)

The figure below is a snap shot from FreeRTOS application using tasks communicating through a queue. Fill the given table with task states (Ready, Running, or Blocked) in consecutive time slots Tx. Show the content of the queue at the end of each slot assuming initial HEX value of $(00\ 00\ 00\ 00\ -00$ 00 00 00 - 00 00 00 00). "Sender 2" is the first running task just after scheduler-start in T1.

```
60 int main ( void )
61 ⊟ {
        xQueue = xQueueCreate( 3, sizeof( long ) );
62
63
       xTaskCreate( vSenderTask, "Sender1", 240, ( void * ) 100, 2, NULL );
       xTaskCreate( vSenderTask, "Sender2", 240, ( void * ) 200, 2, NULL );
64
       xTaskCreate( vReceiverTask, "Receiver", 240, NULL, 1, NULL);
65
        vTaskStartScheduler();
66
67 -}
68
   static void vSenderTask( void *pvParameters )
69 ⊟ {
70
   long lValueToSend;
71 const portTickType xTicksToWait = 100 / portTICK RATE MS;
72
   lValueToSend = ( long ) pvParameters;
73
     for(;;)
74
75
        xQueueSendToBack( xQueue, &lValueToSend, xTicksToWait );
        taskYIELD();
76
77
     }
78 -}
79 static void vReceiverTask( void *pvParameters )
80 □ {
81
   long lReceivedValue;
82
     for( ;; )
83 🖹
84
       xQueueReceive( xQueue, &lReceivedValue, 0 );
85
       vPrintStringAndNumber( "Received = ", lReceivedValue );
86
87 -}
```

	Sender 1	Sender 2	Receiver	Queue Content at The End of Tx Period
T1		Running		C8 00 00 00 00 00 00 00 00 00 00 00
T2		_		
T3				
T4				
T5				
T6				
T7				
T8				
Т9				
T10				
T11				
T12				
T13				
T14				
T15				
T16				

Sherif Hammad P.T.O



June ^{2nd.},2018 Course Code: CSE 345&347 Time: 3 Hours

Real-Time and Embedded Systems Design

Question (6):(8 Marks)

The figure below is a snap shot from a debugging session. Show the sequence of execution timing diagram starting just after vTaskStartScheduler. Tasks should be shown down-up vertically according to their priorities (e.g. Highest priority should be on the top). Also show the debug (printf) viewer.

```
int main ( void )
 82
 83 - {
 84
         vSemaphoreCreateBinary( xBinarySemaphore );
         if ( xBinarySemaphore != NULL )
 85
 86
 87
             prvSetupSoftwareInterrupt();
             xTaskCreate( vHandlerTask, "Handler", 240, NULL, 1, NULL );
 88
 89
             xTaskCreate( vPeriodicTask, "Periodic", 240, NULL, 3, NULL );
 90
             vTaskStartScheduler();
 91
         }
 92 -}
    static void vHandlerTask( void *pvParameters )
 93
 94 ⊟ {
         xSemaphoreTake( xBinarySemaphore, 0 );
 95
 96
         for( ;; )
 97
         {
 98
             xSemaphoreTake( xBinarySemaphore, portMAX_DELAY );
             vPrintString( "Handler task - Processing event.\n" );
99
100
101 |}
102
     static void vPeriodicTask( void *pvParameters )
103 □ {
104
         for( ;; )
105
         {
             vTaskDelay( 500 / portTICK_RATE_MS );
106
107
             vPrintString( "Periodic task - About to generate an interrupt.\n" );
             mainTRIGGER_INTERRUPT();
108
109
             vPrintString( "Periodic task - Interrupt generated.\n\n" );
110
111 |}
112
    void vSoftwareInterruptHandler( void )
113 - {
114
     portBASE_TYPE xHigherPriorityTaskWoken = pdFALSE;
115
         xSemaphoreGiveFromISR( xBinarySemaphore, &xHigherPriorityTaskWoken );
116
         mainCLEAR_INTERRUPT();
         portEND_SWITCHING_ISR( xHigherPriorityTaskWoken );
117
118
```

End of Questions

Sherif Hammad P.T.O