```
BR2 aarch64=v
BR2 ARM FPU VFPV4=v
BR2 CCACHE=y
BR2 RELRO PARTIAL=v
BR2_TOOLCHAIN_BUILDROOT_GLIBC=v
BR2 PACKAGE HOST LINUX HEADERS CUSTOM 4 19=v
BR2_TOOLCHAIN_BUILDROOT_CXX=y
BR2 TARGET GENERIC ISSUE="Welcome to HELL!:)"
BR2 ROOTFS DEVICE CREATION DYNAMIC MDEV=v
BR2_TARGET_GENERIC_ROOT_PASSWD="12345"
BR2 SYSTEM BIN SH BASH=y
BR2 SYSTEM DHCP="eth0"
BR2 ROOTFS OVERLAY="/home/ahmed/Buildroot2/buildroot-2019.11.1/myoverlay"
BR2 ROOTFS POST BUILD SCRIPT="board/raspberrypi3-64/post-build.sh"
BR2_ROOTFS_POST_IMAGE_SCRIPT="board/raspberrypi3-64/post-image.sh"
BR2 ROOTFS POST SCRIPT ARGS="--aarch64"
BR2_LINUX_KERNEL=y
BR2 LINUX KERNEL CUSTOM TARBALL=v
BR2 LINUX KERNEL CUSTOM TARBALL LOCATION="$(call
github,raspberrypi,linux,raspberrypi-kernel_1.20190819-1)/linux-raspberrypi-kernel_1.20190819-
1.tar.gz"
BR2_LINUX_KERNEL_DEFCONFIG="bcmrpi3"
BR2 LINUX KERNEL DTS SUPPORT=v
BR2 LINUX KERNEL INTREE DTS NAME="broadcom/bcm2710-rpi-3-b
broadcom/bcm2710-rpi-3-b-plus broadcom/bcm2837-rpi-3-b"
BR2 LINUX KERNEL NEEDS HOST OPENSSL=v
BR2 PACKAGE BUSYBOX SHOW OTHERS=v
BR2 PACKAGE ALSA UTILS=v
BR2_PACKAGE_ALSA_UTILS_ALSACONF=y
BR2_PACKAGE_ALSA_UTILS_ACONNECT=y
BR2_PACKAGE_ALSA_UTILS_ALSALOOP=y
BR2_PACKAGE_ALSA_UTILS_ALSAUCM=y
BR2_PACKAGE_ALSA_UTILS_ALSATPLG=y
BR2_PACKAGE_ALSA_UTILS_AMIDI=y
BR2_PACKAGE_ALSA_UTILS_AMIXER=y
BR2 PACKAGE ALSA UTILS APLAY=v
BR2_PACKAGE_ALSA_UTILS_APLAYMIDI=y
BR2 PACKAGE ALSA UTILS ARECORDMIDI=v
BR2_PACKAGE_ALSA_UTILS_ASEQDUMP=y
BR2_PACKAGE_ALSA_UTILS_ASEQNET=y
BR2_PACKAGE_ALSA_UTILS_BAT=y
BR2_PACKAGE_ALSA_UTILS_IECSET=y
BR2 PACKAGE ALSA UTILS SPEAKER TEST=v
BR2_PACKAGE_AUMIX=y
BR2_PACKAGE_BLUEZ_ALSA=y
BR2 PACKAGE BLUEZ ALSA HCITOP=v
BR2_PACKAGE_BLUEZ_ALSA_RFCOMM=y
BR2 PACKAGE ESPEAK=y
BR2_PACKAGE_ESPEAK_AUDIO_BACKEND_ALSA=y
BR2_PACKAGE_MODPLUGTOOLS=y
BR2 PACKAGE MPD=v
BR2_PACKAGE_MPD_MPC=y
```

```
BR2 PACKAGE MPG123=v
BR2 PACKAGE PULSEAUDIO=v
BR2 PACKAGE PULSEAUDIO DAEMON=y
BR2 PACKAGE STRACE=v
BR2_PACKAGE_GIT=y
BR2 PACKAGE RPI BT FIRMWARE=v
BR2_PACKAGE_RPI_FIRMWARE=y
# BR2 PACKAGE RPI FIRMWARE INSTALL DTB OVERLAYS is not set
BR2 PACKAGE RPI WIFI FIRMWARE=v
BR2_PACKAGE_AUBIO=y
BR2_PACKAGE_AUDIOFILE=y
BR2 PACKAGE BCG729=v
BR2 PACKAGE LIBMPD=v
BR2 PACKAGE TINYALSA=v
BR2_PACKAGE_NCURSES_WCHAR=y
BR2 PACKAGE NCURSES TARGET PROGS=v
BR2_PACKAGE_BLUEZ_TOOLS=y
BR2 PACKAGE BLUEZ5 UTILS OBEX=v
BR2 PACKAGE BLUEZ5 UTILS CLIENT=v
BR2_PACKAGE_BLUEZ5_UTILS_DEPRECATED=y
BR2_PACKAGE_BLUEZ5_UTILS_EXPERIMENTAL=y
BR2_PACKAGE_BLUEZ5_UTILS_PLUGINS_HEALTH=y
BR2 PACKAGE BLUEZ5 UTILS PLUGINS MIDI=v
BR2_PACKAGE_BLUEZ5_UTILS_PLUGINS_NFC=y
BR2_PACKAGE_BLUEZ5_UTILS_PLUGINS_SAP=y
BR2_PACKAGE_BLUEZ5_UTILS_TEST=y
BR2 PACKAGE DHCP=v
BR2_PACKAGE_DHCP_SERVER=y
BR2_PACKAGE_DHCP_SERVER_DELAYED_ACK=y
BR2_PACKAGE_DHCP_RELAY=y
BR2 PACKAGE DHCP CLIENT=v
BR2_PACKAGE_DHCPCD=y
BR2_PACKAGE_IPTABLES=y
BR2_PACKAGE_IPTABLES_BPF_NFSYNPROXY=y
BR2_PACKAGE_IPTABLES_NFTABLES=y
BR2 PACKAGE OPENSSH=v
BR2_PACKAGE_WGET=y
BR2 PACKAGE WIRELESS TOOLS=v
BR2_PACKAGE_WPA_SUPPLICANT=y
BR2_PACKAGE_WPA_SUPPLICANT_AP_SUPPORT=y
BR2_PACKAGE_WPA_SUPPLICANT_WIFI_DISPLAY=y
BR2_PACKAGE_WPA_SUPPLICANT_AUTOSCAN=y
BR2 PACKAGE WPA SUPPLICANT EAP=y
BR2_PACKAGE_WPA_SUPPLICANT_WPS=y
BR2_PACKAGE_WPA_SUPPLICANT_CLI=y
BR2 PACKAGE WPA SUPPLICANT PASSPHRASE=v
BR2_PACKAGE_SCREEN=y
BR2_PACKAGE_SUDO=y
BR2_PACKAGE_TIME=y
BR2_PACKAGE_UTIL_LINUX=y
BR2 PACKAGE UTIL LINUX KILL=v
BR2_PACKAGE_UTIL_LINUX_MOUNT=y
```

BR2 PACKAGE UTIL LINUX MOUNTPOINT=v

BR2_PACKAGE_UTIL_LINUX_SU=y

BR2_PACKAGE_UTIL_LINUX_SULOGIN=y

BR2_PACKAGE_UTIL_LINUX_SWITCH_ROOT=y

BR2_PACKAGE_UTIL_LINUX_WALL=y

BR2_PACKAGE_UTIL_LINUX_WRITE=y

BR2_PACKAGE_NANO=y

BR2_TARGET_ROOTFS_EXT2=y

BR2_TARGET_ROOTFS_EXT2_4=y

BR2_TARGET_ROOTFS_EXT2_SIZE="600M"

BR2_TARGET_ROOTFS_TAR is not set

BR2_PACKAGE_HOST_DOSFSTOOLS=y

BR2_PACKAGE_HOST_GENIMAGE=y

BR2_PACKAGE_HOST_MTOOLS=y