

# Network Design: Addressing, Subnetting & Topology

Explore the foundational concepts of network design, crucial for building scalable and efficient IT infrastructures. This presentation delves into IP addressing, subnetting, and various network topologies, with a focus on IPv4 and CIDR.

### **Fundamentals of Network Addressing**

1

#### **IP Address Structure**

A 32-bit numerical label assigned to devices in a network, divided into network and host portions to identify both the network and the specific device within it.

2

#### **IPv4 Dotted-Decimal**

IPv4 addresses are expressed in a human-readable dotted-decimal format, such as 192.168.1.1, making them easier to read and remember than binary.

3

#### **Subnet Mask**

A 32-bit number that distinguishes the network portion of an IP address from the host portion, crucial for routing decisions (e.g., 255.255.255.0).


CIDR Notation

Classless Inter-Domain Routing (CIDR) uses a suffix (/24) to denote the number of bits in the network prefix, enabling more flexible and efficient IP address allocation.

# Importance of Proper Addressing

- Unique IPs: Prevent conflicts and enable devices to communicate uniquely on the network, ensuring smooth data exchange.
- Network Portion: Guides packet delivery, ensuring data reaches the correct subnet efficiently, minimizing network congestion.

- Host Portion: Identifies
   individual devices within a
   subnet, allowing precise
   targeting of data packets to
   their destinations.
- Efficiency & Security:
   Reduces IP waste, simplifies
   network management, and
   enhances security by
   limiting broadcast domains.



# What is Subnetting?

Subnetting is the strategic division of a larger IP network into smaller, more manageable subnetworks. This process involves "borrowing" bits from the host portion of an IP address to create new subnet identifiers.

 $\left.\begin{array}{ccc} 1 & & \\ \end{array}\right>$ 

#### **Traffic Management**

Enhances network performance by localizing traffic within smaller broadcast domains, reducing overall network congestion.

#### **Enhanced Security**

Allows for the isolation of sensitive network segments, limiting access and preventing unauthorized users from reaching critical resources.


#### **Improved Scalability**

Facilitates easier expansion and organization of networks, making it simpler to add new devices or departments without a complete overhaul.

# Subnetting Calculations & Formulas

Understanding these formulas is key to successfully segmenting networks and optimizing IP address utilization. Mastering them allows for efficient allocation and management of network resources.

Number of Subnets	$2^{\Delta}x$ (where x is the number of bits borrowed from the host portion)
Hosts per Subnet	$2^{4}y$ - $2$ (where y is the number of remaining host bits, minus network and broadcast addresses)
Block Size	256 - \text{Subnet Mask Octet Value} (determines the increment between subnets)
Broadcast Address	The last usable address in a given subnet range



# **Subnetting Example:** 192.168.1.0/24 to /26

By borrowing two bits from the host portion of the 192.168.1.0/24 network, we can create four distinct subnets, each supporting 62 usable hosts. This segmentation enhances efficiency and management.

#### **Calculations**

- Bits Borrowed: 2
- Number of Subnets:  $2^2 = 4$
- Hosts per Subnet: 2^(8-2) 2 =
  62 usable hosts
- Subnet Mask: 255.255.255.192

#### **Subnet Ranges**

- Subnet 0: 192.168.1.0 192.168.1.63
- Subnet 1: 192.168.1.64 192.168.1.127
- Subnet 2: 192.168.1.128 192.168.1.191
- Subnet 3: 192.168.1.192 192.168.1.255

## **Advanced Subnetting Concepts**

Advanced subnetting techniques are crucial for optimizing large and complex network architectures, ensuring efficient resource allocation and superior performance.

#### **CIDR (Classless Inter-Domain Routing)**

Allows flexible prefix lengths that transcend traditional classful boundaries, improving IP address utilization and routing efficiency across the internet.

#### **Special Subnets**

Includes /30 for point-to-point links (minimizing address usage) and /32 for loopback interfaces (ensuring stable routing independent of physical interfaces).

#### **VLSM (Variable Length Subnet Mask)**


Enables the use of different subnet sizes within the same network, tailoring addressing to specific needs and preventing IP address waste in varied network segments.


#### **Broadcast Domain Reduction**

Subnetting significantly reduces the size of broadcast domains, minimizing unnecessary traffic and enhancing network performance and security by limiting message propagation.

# **Network Topology Overview**







#### **Physical Topology**

Describes the actual physical layout of network devices, cables, and connections, showing how components are wired together.

#### **Logical Topology**

Defines how data flows through the network, regardless of the physical arrangement, illustrating the communication paths between devices.

#### **Common Types**

Includes well-known structures like
Bus, Star, Ring, Mesh, Tree, and
Hybrid topologies, each with distinct
advantages for network design.

## **Topology & Addressing Design Considerations**

The choice of network topology directly influences addressing schemes and overall network performance, impacting scalability, fault tolerance, and cost efficiency.

#### **Bus Topology**

Typically uses a single subnet with minimal IP addresses, suitable for small, simple networks where all devices share a common communication line.

#### **Star Topology**

Requires unique IP ranges per device connected to a central hub or switch, offering better fault isolation and easier troubleshooting.

#### **Mesh Topology**

Benefits from hierarchical addressing for core and edge devices, providing high redundancy and fault tolerance but with increased complexity.

#### **Tree & Hybrid Topologies**

Tree topologies utilize subnet branches for scalable management, while hybrid models combine multiple topologies and addressing schemes to meet diverse network requirements.

# Summary & Best Practices Strategic Network Foundations

- Addressing: Design IP schemes to align with network size and future growth plans, ensuring ample room for
  expansion without re-addressing.
- Subnetting: Implement subnetting to optimize IP usage, enhance security by segmenting networks, and improve performance by reducing broadcast traffic.
- Topology: Select the appropriate topology based on requirements for fault tolerance, scalability, cost-effectiveness, and ease of management.
- Integration: Ensure IP schemes are meticulously planned and aligned with the chosen topology for seamless integration and efficient routing.