Tempo



# INTALIOInternationalization and customization of the UI-FW

Log In

<u>V</u>iew <u>A</u>ttachments (1) <u>I</u>nfo

Browse Space

Added by Nicolas Modrzyk, last edited by Nicolas Modrzyk on Oct 31, 2008

# **Customization of the UI-FW**

#### Modifying the intro page.

You can edit and modify at will the welcome page by editing the following page: http://tempo.intalio.org/tempo/trunk/ui-fw/src/main/webapp/customize/intro.jsp

Or in the server, within the ui-fw application folder:

webapp/customize/intro.jsp

#### Welcome to TEMPO

Start your session by clicking on the tab you want to start working with. You can find more information on the tempo website. And of course, find your best samples and tutorials at the Intalio Library.

# Internationalization of the UI-FW

### Modifying the default language settings

To Modify the default language ( in this example, we are going to set the language as japanese ):

- Open the file SERVER PATH\var\config\tempo-ui-fw.xml.
- Add the following bean in the "beans" tag :

<bean id="localeResolver" class="org.springframework.web.servlet.i18n.FixedLocaleResolver"> cproperty name="defaultLocale" value="ja" /> </bean>

• Restart your server.

If you want to set the language according to the language of the user (the language settings of the browser):

- Open the file SERVER\_PATH\var\config\tempo-ui-fw.xml.
- Add the following bean in the "beans" tag :

<br/>
<br/>
dean id="localeResolver" class = "org.spring framework.web.servlet.i18n. Accept Header Locale Resolver" > 1000 Grand Resolver = 10000</bean>

• Restart your server.

## Adding another language

The Intalio UI-FW currently supports an english and japanese versions. To add another language:

- 1. Go to SERVER PATH\repository\org\intalio\tempo\ui-fw\5.2.0.19\ui-fw-5.2.0.19.war\WEB-INF\classes ( the path will slightly change depending on your server version).
- 2. copy and paste messages\_en.properties and rename it. ( messages\_fr.properties for french, messages\_sp.properties for spanish...).
- 3. Translate the values of the properties in the file.
- 4. Modify the default language settings ( see above).
- 5. restart your server.

#### **Comments**

Learn more or evaluate Confluence for your organisation.

 $Powered \ by \ \underline{Atlassian \ Confluence}, the \ \underline{Enterprise \ Wiki}. \ (Version: 1.4.1 \ Build: \#212 \ Jun \ 02, 2005) \ - \ \underline{Bug/feature \ request} \ - \ \underline{Contact \ Administrators}$