



XIQ API – Permission Requirements and User Roles

25 Feb 2026
Version 25r7

Revisions History

Rev	Revision Summary	By Whom	Publish Date
25r5	25r5 Updates	Tim	Sept 22, 2025
25r6	25r6 Updates	Tim	Nov 13, 2025
25r7	25r7 Updates	Tim	Feb 25, 2026

Table of Contents

Introduction.....	23
Authentication.....	24
POST /login.....	24
POST /logout.....	24
Authorization.....	24
POST /auth/apitoken.....	24
POST /auth/apitoken/:validate.....	24
GET /auth/apitoken/info.....	25
GET /auth/permissions.....	25
POST /auth/permissions/:check.....	25
GET /operations/{operationId}.....	25
DELETE /operations/{operationId}.....	25
POST /operations/{operationId}/:cancel.....	26
Operation.....	26
GET /operations/{operation id}.....	26
DELETE /operations/{operation id}.....	26
POST /operations/{operation id}/:cancel.....	26
Account.....	26
POST /account/:switch.....	27
GET /account/external.....	27
GET /account/home.....	27
GET /account/third-party-applications.....	27
GET /account/vhm/setting.....	28
PUT /account/vhm/setting/{id}.....	28
GET /account/vhm/setting/status.....	28
GET /account/viq.....	28
POST /account/viq/:backup.....	29
POST /account/viq/:reset.....	29
GET /account/viq/default-device-password.....	29
PUT /account/viq/default-device-password.....	29
GET /account/viq/download.....	29
POST /account/viq/export.....	30
GET /account/viq/export-import-status.....	30
POST /account/viq/import.....	30
POST /backup/history/:restore.....	30
POST /backup/history/delete.....	31
GET /backup/history/grid.....	31
PUT /backup/history/grid.....	31
Users.....	31
GET /users.....	31
POST /users.....	31
GET /users/{id}.....	31
DELETE /users/{id}.....	32
PATCH /users/{id}.....	32
POST /users/data-usage.....	32

GET /users/external.....	32
POST /users/external.....	32
GET /users/external/{id}.....	32
DELETE /users/external/{id}.....	32
PATCH /users/external/{id}.....	33
POST /users/filter-metadata.....	33
POST /users/grid.....	33
POST /users/grid-export.....	33
GET /users/me.....	33
GET /users/report/{id}.....	34
POST /users/type-distribution.....	34
Use Folder Preferences.....	34
GET /user-folder-preferences.....	34
POST /user-folder-preferences/:folderId.....	34
HIQ.....	35
GET /hiq/context.....	35
PUT /hiq/context.....	35
GET /hiq/context/creating.....	35
PUT /hiq/context/creating.....	35
GET /hiq/context/reading.....	36
PUT /hiq/context/reading.....	36
GET /hiq/organizations.....	36
POST /hiq/organizations.....	36
DELETE /hiq/organizations/{id}.....	37
POST /hiq/organizations/{id}/:rename.....	37
GET /hiq/status.....	37
Location.....	37
POST /locations.....	37
POST /locations/:init.....	38
PUT /locations/{id}.....	38
DELETE /locations/{id}.....	38
GET /locations/building.....	38
POST /locations/building.....	38
GET /locations/building/{id}.....	39
PUT /locations/building/{id}.....	39
DELETE /locations/building/{id}.....	39
GET /locations/floor.....	39
POST /locations/floor.....	39
GET /locations/floor/{floorId}/label.....	40
PUT /locations/floor/{floorId}/label.....	40
POST /locations/floor/{floorId}/label.....	40
DELETE /locations/floor/{floorId}/label/{labelId}.....	40
GET /locations/floor/{id}.....	40
PUT /locations/floor/{id}.....	41
DELETE /locations/floor/{id}.....	41
PUT /locations/floor/bulk/label.....	41
POST /locations/floorplan.....	41
GET /locations/folder/zone/{id}.....	41
DELETE /locations/folder/zone/{id}.....	42

PUT /locations/folder/zone.....	42
POST /locations/folder/zone.....	42
POST /locations/import/ekahau.....	42
GET /locations/site.....	42
POST /locations/site.....	43
GET /locations/site/{id}.....	43
PUT /locations/site/{id}.....	43
DELETE /locations/site/{id}.....	43
GET /locations/tree.....	43
GET /locations/tree/devices.....	44
GET /locations/tree/maps.....	44
GET /locations/wall/type.....	44
POST /locations/wall/type.....	44
PUT /locations/wall/type/{id}.....	44
DELETE /locations/wall/type/{id}.....	45
GET /locations/wall/type/references/{id}.....	45
Device.....	45
GET /devices.....	45
POST /devices/:advanced-onboard.....	45
POST /devices/:check-ownership.....	46
POST /devices/:cli.....	46
POST /devices/:delete.....	46
POST /devices/:manage.....	46
POST /devices/:onboard.....	46
POST /devices/:reboot.....	47
POST /devices/:reset.....	47
POST /devices/:ssh-active-sessions.....	47
POST /devices/:unmanage.....	47
GET /devices/{id}.....	47
DELETE /devices/{id}.....	48
POST /devices/{id}/:cli.....	48
POST /devices/{id}/:manage.....	48
POST /devices/{id}/:reboot.....	48
POST /devices/{id}/:reset.....	48
POST /devices/{id}/:unmanage.....	48
GET /devices/{id}/alarms.....	49
POST /devices/{id}/bounce-port.....	49
GET /devices/{id}/client-monitor.....	49
PUT /devices/{id}/client-monitor.....	49
DELETE /devices/{id}/client-monitor.....	49
PUT /devices/{id}/description.....	50
GET /devices/{id}/ftm-settings.....	50
POST /devices/{id}/config/ftm-settings.....	50
DELETE /devices/{id}/config/ftm-settings.....	50
GET /devices/{id}/gallery-image.....	50
GET /devices/{id}/geolocation.....	50
GET /devices/{id}/history/cpu-mem.....	51
PUT /devices/{id}/hostname.....	51
GET /devices/{id}/ibeacon.....	51
GET /devices/{id}/installation-report.....	51

GET /devices/{id}/interfaces/wifi.....	52
GET /devices/{id}/iot.....	52
POST /devices/{id}/iot:disable.....	52
POST /devices/{id}/iot:enable.....	52
GET /devices/{id}/location.....	52
PUT /devices/{id}/location.....	53
DELETE /devices/{id}/location.....	53
PUT /devices/{id}/mobileapp/gps.....	53
POST /devices/{id}/monitor:refresh.....	53
GET /devices/{id}/monitor/refresh/status.....	53
GET /devices/{id}/network-policy.....	53
PUT /devices/{id}/network-policy.....	54
DELETE /devices/{id}/network-policy.....	54
GET /devices/{id}/radio-operating-mode.....	54
PUT /devices/{id}/radio-operating-mode.....	54
POST /devices/{id}/ssid:override.....	54
GET /devices/{id}/ssid/status.....	55
POST /devices/{id}/ssid/status/:change.....	55
POST /devices/{id}/thread/commissioner:start.....	55
POST /devices/{id}/thread/commissioner:stop.....	55
PUT /devices/{id}/thread/visible.....	55
POST /devices/actions-support-metadata.....	56
POST /devices/anchor/assign.....	56
POST /devices/anchor/revoke.....	56
POST /devices/client-monitor/:assign.....	56
POST /devices/client-monitor/:revoke.....	56
POST /devices/client-monitor:query.....	56
POST /devices/country-code/:assign.....	57
GET /devices/{id}/digital-twin.....	57
PUT /devices/ibeacon.....	57
POST /devices/location/:assign.....	57
POST /devices/location:query.....	57
POST /devices/location:revoke.....	58
POST /devices/network-policy/:assign.....	58
POST /devices/network-policy/:query.....	58
POST /devices/network-policy:revoke.....	58
GET /devices/network-policy/{policyId}.....	58
POST /devices/os/:change.....	58
GET /devices/radio-information.....	59
PUT /devices/radius-proxy:assign.....	59
DELETE /devices/radius-proxy:revoke.....	59
GET /devices/reports/{id}.....	59
POST /devices/rm-devices-connection-status.....	59
POST /devices/rm-devices-metadata.....	60
POST /devices/rm-devices-page.....	60
POST /devices/rm-devices-page/export.....	60
GET /devices/rm-devices-stack/{id}.....	60
GET /devices/stats.....	61
POST /devices/thread/commissioner/start.....	61
POST /devices/thread/commissioner/stop.....	61

Network Policy.....	61
GET /network-policies.....	61
POST /network-policies.....	62
GET /network-policies/{id}.....	62
PUT /network-policies/{id}.....	62
DELETE /network-policies/{id}.....	62
GET /network-policies/{id}/ssids.....	62
POST /network-policies/{id}/ssids/:add.....	62
POST /network-policies/{id}/ssids/:remove.....	63
Client.....	63
GET /clients/{id}.....	63
GET /clients/active.....	63
PUT /clients/alias.....	63
GET /clients/active/count.....	64
GET /clients/byMac/{client_mac}.....	64
DELETE /clients/byMac/{client_mac}.....	64
POST /clients/disconnect.....	64
GET /clients/summary.....	64
GET /clients/usage.....	65
Client - Details.....	65
GET /client-details/client-trail/connectivity-experience/{id}.....	65
GET /client-details/client-trail/roaming-trail/count/{id}.....	65
GET /client-details/client-trail/roaming-trail/grid/{id}.....	65
GET /client-details/overview/chart-data/{id}.....	65
GET /client-details/overview/info/{id}.....	65
GET /client-details/topology/client-trail/{client_mac}.....	66
Switch Inspector Panel.....	66
POST /switch-inspector/diagnostics.....	66
D360.....	66
POST /d360/client/graph.....	66
POST /d360/client/grid.....	66
POST /d360/client/grid/metadata.....	67
POST /d360/client/stats.....	67
POST /d360/device/interfaces.....	67
POST /d360/device/issues.....	67
POST /d360/device/metadata.....	67
POST /d360/device/stats.....	67
POST /d360/event/graph.....	67
POST /d360/overview/devices-summary.....	67
POST /d360/ssid-metadata.....	68
POST /d360/wired/queue-grid.....	68
POST /d360/wireless/interfaces-graph.....	68
POST /d360/wireless/interfaces-stats.....	68
POST /d360/wireless/surrounding-aps.....	68
Dashboard.....	68
POST /dashboard/alerts.....	68
POST /dashboard/assets.....	69

POST /dashboard/clients.....	69
GET /dashboard/device-types.....	69
POST /dashboard/devices.....	69
POST /dashboard/export.....	69
GET /dashboard/reports/{id}.....	70
POST /dashboard/sites-with-issues.....	70
POST /dashboard/usage-capacity.....	70
GET /dashboard/wireless/dashboard/criteria.....	70
POST /dashboard/wireless/dashboard/criteria.....	70
Dashboard Wired Usage and Capacity.....	71
POST /dashboard/wired/usage-capacity/grid.....	71
POST /dashboard/wired/usage-capacity/usage-utilization.....	71
POST /dashboard/wired/usage-capacity/wired-congestion.....	71
POST /dashboard/wired/usage-capacity/wired-throughput.....	71
Dashboard Wired Client Health.....	72
POST /dashboard/wired/client-health/grid.....	72
POST /dashboard/wired/client-health/ip-connectivity-issues.....	72
POST /dashboard/wired/client-health/port-congestion.....	72
POST /dashboard/wired/client-health/port-errors.....	72
POST /dashboard/wired/client-health/traffic-anomalies.....	72
Dashboard Wired Device Health.....	73
POST /dashboard/wired/device-health/cpu-usage-issues.....	73
POST /dashboard/wired/device-health/fan-issues.....	73
POST /dashboard/wired/device-health/fan-status.....	73
POST /dashboard/wired/device-health/grid.....	73
POST /dashboard/wired/device-health/memory-usage-issues.....	74
POST /dashboard/wired/device-health/poe-usage-issues.....	74
POST /dashboard/wired/device-health/poe-usage-status.....	74
POST /dashboard/wired/device-health/psu-issues.....	74
POST /dashboard/wired/device-health/psu-status.....	75
POST /dashboard/wired/device-health/summary.....	75
POST /dashboard/wired/device-health/temperature-issues.....	75
POST /dashboard/wired/device-health/temperature-status.....	75
Dashboard Wireless Usage and Capacity.....	75
POST /dashboard/wireless/usage-capacity/excessive-packet-loss.....	75
POST /dashboard/wireless/usage-capacity/excessive-retries.....	76
POST /dashboard/wireless/usage-capacity/excessive-utilization.....	76
POST /dashboard/wireless/usage-capacity/export.....	76
POST /dashboard/wireless/usage-capacity/grid.....	76
GET /dashboard/wireless/usage-capacity/reports/{id}.....	77
Dashboard Wireless Client Health.....	77
POST /dashboard/wireless/client-health/connectivity-issues.....	77
POST /dashboard/wireless/client-health/export.....	77
POST /dashboard/wireless/client-health/filter-metadata.....	77
POST /dashboard/wireless/client-health/frequency-distribution.....	77
POST /dashboard/wireless/client-health/grid.....	78
POST /dashboard/wireless/client-health/issue/association.....	78

POST /dashboard/wireless/client-health/issue/authentication.....	78
POST /dashboard/wireless/client-health/issue/ipaddress.....	78
POST /dashboard/wireless/client-health/issue/roaming.....	79
GET /dashboard/wireless/client-health/reports/{id}.....	79
POST /dashboard/wireless/client-health/roaming-issues.....	79
Dashboard Wireless Device Health.....	79
POST /dashboard/wireless/device-health/export.....	79
POST /dashboard/wireless/device-health/grid.....	79
POST /dashboard/wireless/device-health/cpu-usage-issues.....	80
POST /dashboard/wireless/device-health/memory-usage-issues.....	80
POST /dashboard/wireless/device-health/poe-usage-issues.....	80
GET /dashboard/wireless/device-health/reports/{id}.....	80
GET /dashboard/wireless/device-health/reboot/summary.....	80
POST /dashboard/wireless/device-health/summary.....	81
Geo View.....	81
GET /geo-view.....	81
Application.....	81
GET /applications.....	81
GET /applications/{id}/clients/top{n}.....	81
GET /applications/reports/{id}.....	82
GET /applications/top{n}.....	82
POST /applications/usage/summary.....	82
POST /applications/usage/summary/export.....	82
GET /applications/usage/summary/meta-data.....	83
Alert.....	83
GET /alert-policies.....	83
POST /alert-policies.....	83
GET /alert-policies/{id}.....	83
PUT /alert-policies/{id}.....	84
DELETE /alert-policies/{id}.....	84
GET /alert-policies/{id}/rules/{alert_rule_id}.....	84
PUT /alert-policies/{id}/rules/{alert_rule_id}.....	84
POST /alert-policies/{id}/rules/{alert_rule_id}/:disable.....	84
PUT /alert-policies/{id}/rules/{alert_rule_id}/:enable.....	84
GET /alert-policies/available-sites.....	85
GET /alert-subscriptions/emails.....	85
POST /alert-subscriptions/emails.....	85
POST /alert-subscriptions/emails/:delete.....	85
GET /alert-subscriptions/emails/{id}.....	85
PUT /alert-subscriptions/emails/{id}.....	86
DELETE /alert-subscriptions/emails/{id}.....	86
POST /alert-subscriptions/emails/{id}/:verify.....	86
GET /alert-subscriptions/servicenow.....	86
POST /alert-subscriptions/servicenow.....	86
POST /alert-subscriptions/servicenow/:delete.....	86
GET /alert-subscriptions/servicenow/{id}.....	87
PUT /alert-subscriptions/servicenow/{id}.....	87
PATCH /alert-subscriptions/servicenow/{id}.....	87

GET /alert-subscriptions/webhooks.....	87
POST /alert-subscriptions/webhooks.....	87
POST /alert-subscriptions/webhooks/:delete.....	88
GET /alert-subscriptions/webhooks/{id}.....	88
PUT /alert-subscriptions/webhooks/{id}.....	88
DELETE /alert-subscriptions/webhooks/{id}.....	88
GET /alerts.....	88
POST /alerts/:acknowledge.....	89
GET /alerts/count-by-{group}.....	89
POST /alerts/report.....	89
GET /alerts/reports/{id}.....	89
Log.....	89
GET /logs/accounting.....	90
GET /logs/audit.....	90
GET /logs/audit/full-descriptions/{id}.....	90
POST /logs/audit/reports.....	90
GET /logs/audit/reports/{id}.....	90
GET /logs/auth.....	91
GET /logs/credential.....	91
GET /logs/email.....	91
GET /logs/sms.....	91
Notification.....	92
GET /subscriptions/webhook.....	92
POST /subscriptions/webhook.....	92
DELETE /subscriptions/webhook/:delete.....	92
PUT /subscriptions/webhook/{id}.....	92
GET /subscriptions/webhook/export.....	92
Administration.....	93
GET /acct-api-token.....	93
POST /acct-api-token.....	93
DELETE /acct-api-token/:delete.....	93
DELETE /acct-api-token/{id}.....	93
PATCH /acct-api-token/{id}.....	93
GET /acct-api-token/export.....	94
GET /credential-distribution-groups.....	94
POST /credential-distribution-groups.....	94
DELETE /credential-distribution-groups.....	94
PUT /credential-distribution-groups/{id}.....	94
GET /third-party-api-connection.....	95
PUT /third-party-api-connection.....	95
DELETE /third-party-api-connection.....	95
NOS.....	95
Configuration - Deployment.....	95
GET /deployments.....	95
POST /deployments.....	96
GET /deployments/{id}.....	96
PUT /deployments/{id}.....	96

DELETE /deployments/{id}.....	96
GET /deployments/{id}/status.....	96
POST /deployments/firmware-metadatas.....	97
GET /deployments/overview.....	97
GET /deployments/status.....	97
Configuration - Basic.....	97
GET /vlan-profiles.....	97
POST /vlan-profiles.....	98
POST /vlan-profiles/:delete.....	98
GET /vlan-profiles/{id}.....	98
DELETE /vlan-profiles/{id}.....	98
PATCH /vlan-profiles/{id}.....	98
Configuration - User Management.....	98
GET /email-templates.....	98
GET /endusers.....	99
POST /endusers.....	99
PUT /endusers/{id}.....	99
DELETE /endusers/{id}.....	99
POST /endusers/{id}/:regenerate-password.....	99
GET /pcgs/key-based.....	100
POST /pcgs/key-based.....	100
DELETE /pcgs/key-based/network-policy-{policyId}.....	100
POST /pcgs/key-based/network-policy-{policyId}/:onboard.....	100
POST /pcgs/key-based/network-policy-{policyId}/keys/:email.....	100
POST /pcgs/key-based/network-policy-{policyId}/keys/:generate.....	100
GET /pcgs/key-based/network-policy-{policyId}/port-assignments.....	101
POST /pcgs/key-based/network-policy-{policyId}/port-assignments.....	101
GET /pcgs/key-based/network-policy-{policyId}/users.....	101
PUT /pcgs/key-based/network-policy-{policyId}/users.....	101
POST /pcgs/key-based/network-policy-{policyId}/users.....	101
DELETE /pcgs/key-based/network-policy-{policyId}/users.....	102
GET /sms-templates.....	102
GET /usergroups.....	102
POST /usergroups.....	102
GET /usergroups/:unique.....	102
PUT /usergroups/{id}.....	103
DELETE /usergroups/{id}.....	103
Configuration - Policy.....	103
GET /ccgs.....	103
POST /ccgs.....	103
GET /ccgs/{id}.....	103
PUT /ccgs/{id}.....	104
DELETE /ccgs/{id}.....	104
GET /classification-rules.....	104
POST /classification-rules.....	104
GET /classification-rules/{id}.....	104
PUT /classification-rules/{id}.....	104
DELETE /classification-rules/{id}.....	105
GET /client-monitor-profiles.....	105

POST /client-monitor-profile.....	105
GET /client-monitor-profile/{id}.....	105
PUT /client-monitor-profile/{id}.....	105
DELETE /client-monitor-profile/{id}.....	106
GET /hotspot-profiles.....	106
POST /hotspot-profiles.....	106
GET /hotspot-profiles/{id}.....	106
PUT /hotspot-profiles/{id}.....	106
DELETE /hotspot-profiles/{id}.....	106
GET /hotspot-service-provider-profiles.....	107
POST /hotspot-service-provider-profiles.....	107
GET /hotspot-service-provider-profiles/{id}.....	107
PUT /hotspot-service-provider-profiles/{id}.....	107
DELETE /hotspot-service-provider-profiles/{id}.....	108
GET /iot-profiles.....	108
POST /iot-profiles.....	108
GET /iot-profiles/{id}.....	108
PUT /iot-profiles/{id}.....	108
DELETE /iot-profiles/{id}.....	109
GET /ip-firewall-policies.....	109
POST /ip-firewall-policies.....	109
GET /ip-firewall-policies/{id}.....	109
PUT /ip-firewall-policies/{id}.....	109
DELETE /ip-firewall-policies/{id}.....	110
POST /ip-firewall-policies/{id}/attach.....	110
POST /ip-firewall-policies/{id}/detach.....	110
GET /l3-address-profiles.....	110
POST /l3-address-profiles.....	110
GET /l3-address-profiles/{id}.....	110
PUT /l3-address-profiles/{id}.....	111
DELETE /l3-address-profiles/{id}.....	111
GET /mac-firewall-policies.....	111
POST /mac-firewall-policies.....	111
GET /mac-firewall-policies/{id}.....	111
PUT /mac-firewall-policies/{id}.....	112
DELETE /mac-firewall-policies/{id}.....	112
POST /mac-firewall-policies/{id}/attach.....	112
POST /mac-firewall-policies/{id}/detach.....	112
GET /mac-object-profiles.....	112
POST /mac-object-profiles.....	112
GET /mac-object-profiles/{id}.....	113
PUT /mac-object-profiles/{id}.....	113
DELETE /mac-object-profiles/{id}.....	113
GET /radio-operating-modes/{id}.....	113
GET /radio-profiles.....	113
POST /radio-profiles.....	113
GET /radio-profiles/{id}.....	114
PUT /radio-profiles/{id}.....	114
DELETE /radio-profiles/{id}.....	114
GET /radio-profiles/channel-selection/{channel-selection-id}.....	114
PUT /radio-profiles/channel-selection/{channel-selection-id}.....	114

GET /radio-profiles/mac-ouis.....	115
POST /radio-profiles/mac-ouis.....	115
GET /radio-profiles/mac-ouis/{mac-oui-id}.....	115
PUT /radio-profiles/mac-ouis/{mac-oui-id}.....	115
DELETE /radio-profiles/mac-ouis/{mac-oui-id}.....	115
GET /radio-profiles/miscellaneous/{radio-misc-id}.....	116
PUT /radio-profiles/miscellaneous/{radio-misc-id}.....	116
GET /radio-profiles/neighborhood-analysis/{neigh-analysis-id}.....	116
PUT /radio-profiles/neighborhood-analysis/{neigh-analysis-id}.....	116
GET /radio-profiles/radio-usage-opt/{radio-usage-opt-id}.....	116
PUT /radio-profiles/radio-usage-opt/{radio-usage-opt-id}.....	117
GET /radio-profiles/sensor-scan/{sensor-scan-id}.....	117
PUT /radio-profiles/sensor-scan/{sensor-scan-id}.....	117
GET /radio-profiles/wmm-qos/{radio-qos-id}.....	117
PUT /radio-profiles/wmm-qos/{radio-qos-id}.....	117
GET /ssids.....	118
POST /ssids/{id}/:rename.....	118
POST /ssids/{id}/client-monitor-profile/:attach.....	118
POST /ssids/{id}/cwp/:attach.....	118
POST /ssids/{id}/cwp/:disable.....	118
POST /ssids/{id}/cwp/:enable.....	118
PUT /ssids/{id}/mode/dot1x.....	119
PUT /ssids/{id}/mode/open.....	119
PUT /ssids/{id}/mode/ppsk.....	119
PUT /ssids/{id}/mode/psk.....	119
PUT /ssids/{id}/mode/wep.....	119
PUT /ssids/{id}/psk/password.....	119
POST /ssids/{id}/radius-client-profile.....	119
POST /ssids/{id}/radius-server-group/:attach.....	120
POST /ssids/{id}/user-profile-assignment.....	120
POST /ssids/{id}/user-profile/:attach.....	120
GET /ssids/advanced-settings/{id}.....	120
PUT /ssids/advanced-settings/{id}.....	120
GET /user-profile-assignments.....	120
POST /user-profile-assignments.....	121
GET /user-profile-assignments/{id}.....	121
DELETE /user-profile-assignments/{id}.....	121
GET /user-profiles.....	121
POST /user-profiles.....	122
GET /user-profiles/{id}.....	122
PUT /user-profiles/{id}.....	122
DELETE /user-profiles/{id}.....	122
POST /user-profiles/{id}/ip-firewall-policies/:attach.....	122
POST /user-profiles/{id}/ip-firewall-policies/:detach.....	122
POST /user-profiles/{id}/mac-firewall-policies/:attach.....	123
POST /user-profiles/{id}/,ac-firewall-policies/:detach.....	123
Configuration - Network.....	123
GET /network-services.....	123
POST /network-services.....	123
DELETE /network-services/{id}.....	123

GET /tunnel-concentrators.....	124
POST /tunnel-concentrators.....	124
GET /tunnel-concentrators/{id}.....	124
PUT /tunnel-concentrators/{id}.....	124
DELETE /tunnel-concentrators/{id}.....	124
Configuration - Authentication.....	124
GET /ad-servers.....	125
GET /cwps.....	125
GET /ldap-servers.....	125
POST /ldap-servers.....	125
GET /ldap-servers/{id}.....	125
PUT /ldap-servers/{id}.....	126
DELETE /ldap-servers/{id}.....	126
GET /radius-client-objects.....	126
POST /radius-client-objects.....	126
GET /radius-client-objects/{id}.....	126
PUT /radius-client-objects/{id}.....	127
DELETE /radius-client-objects/{id}.....	127
GET /radius-proxies.....	127
POST /radius-proxies.....	127
GET /radius-proxies/{id}.....	127
PUT /radius-proxies/{id}.....	127
DELETE /radius-proxies/{id}.....	128
GET /radius-proxies/devices.....	128
GET /radius-servers/external.....	128
POST /radius-servers/external.....	128
GET /radius-servers/external/{id}.....	128
PUT /radius-servers/external/{id}.....	129
DELETE /radius-servers/external/{id}.....	129
GET /radius-servers/internal.....	129
POST /radius-servers/internal.....	129
DELETE /radius-servers/internal.....	129
GET /radius-servers/internal/{id}.....	129
PUT /radius-servers/internal/{id}.....	130
DELETE /radius-servers/internal/{id}.....	130
GET /radius-servers/internal/devices.....	130
GET /radsec-proxies.....	130
POST /radsec-proxies.....	131
GET /radsec-proxies/{id}.....	131
PUT /radsec-proxies/{id}.....	131
DELETE /radsec-proxies/{id}.....	131
Configuration - Certificate.....	131
GET /certificate-bundle.....	131
POST /certificate-bundle.....	132
GET /certificate-bundle/{id}.....	132
PUT /certificate-bundle/{id}.....	132
DELETE /certificate-bundle/{id}.....	132
GET /certificates.....	132
DELETE /certificates/{id}.....	133

POST /certificates/import.....	133
Copilot - Connectivity Experience.....	133
GET /copilot/connectivity/client-type.....	133
GET /copilot/connectivity/locations.....	133
GET /copilot/connectivity/wired/events.....	133
GET /copilot/connectivity/wired/experience.....	133
GET /copilot/connectivity/wired/hardware.....	134
GET /copilot/connectivity/wired/locations/hardware.....	134
GET /copilot/connectivity/wired/quality-index.....	134
GET /copilot/connectivity/wireless/apps.....	134
GET /copilot/connectivity/wireless/events.....	134
GET /copilot/connectivity/wireless/experience.....	135
GET /copilot/connectivity/wireless/locations/events.....	135
GET /copilot/connectivity/wireless/locations/performance.....	135
GET /copilot/connectivity/wireless/locations/quality-index.....	135
GET /copilot/connectivity/wireless/locations/time-to-connect.....	136
GET /copilot/connectivity/wireless/performance.....	136
GET /copilot/connectivity/wireless/quality-index.....	136
GET /copilot/connectivity/wireless/time-to-connect.....	136
GET /copilot/connectivity/wireless/views.....	136
Copilot - Anomalies.....	137
GET /copilot/anomalies/adverse-traffic/device-stats.....	137
GET /copilot/anomalies/adverse-traffic/packet-counts.....	137
GET /copilot/anomalies/anomalies-by-category.....	137
GET /copilot/anomalies/device-by-location.....	137
GET /copilot/anomalies/device-with-locations.....	138
PUT /copilot/anomalies/devices/feedback.....	138
PUT /copilot/anomalies/devices/update-action.....	138
GET /copilot/anomalies/dfs-recurrence/channel-stats.....	138
GET /copilot/anomalies/dfs-recurrence/count-stats.....	138
POST /copilot/anomalies/exclude-vlans.....	139
POST /copilot/anomalies/exclude-vlans-csv.....	139
GET /copilot/anomalies/exclude-vlans-list.....	139
GET /copilot/anomalies/hardware-health/client-list.....	139
GET /copilot/anomalies/hardware-health/cpu-mem-stats.....	139
GET /copilot/anomalies/hardware-health/stats.....	140
GET /copilot/anomalies/locations.....	140
GET /copilot/anomalies/missing-vlan/count.....	140
GET /copilot/anomalies/notifications.....	140
GET /copilot/anomalies/poeflapping/ldp-cdp-info.....	140
GET /copilot/anomalies/poeflapping/stats.....	141
GET /copilot/anomalies/poeflapping/trends.....	141
GET /copilot/anomalies/port-efficiency/speed-duplex-stats.....	141
GET /copilot/anomalies/port-efficiency/stats.....	141
GET /copilot/anomalies/wifi-capacity/client-list.....	141
GET /copilot/anomalies/wifi-capacity/stats.....	142
GET /copilot/anomalies/report.....	142
PUT /copilot/anomalies/update-action.....	142
PUT /copilot/anomalies/update-device-action.....	142

GET /copilot/anomalies/wifi-efficiency/client-list.....	142
GET /copilot/anomalies/wifi-efficiency/stats.....	143
GET /copilot/assurance-scans/overview.....	143
Packet Capture.....	143
GET /packetcaptures.....	143
POST /packetcaptures.....	143
DELETE /packetcaptures.....	144
GET /packetcaptures/{id}.....	144
Delete /packetcaptures/{id}.....	144
POST /packetcaptures/{id}/:stop.....	144
POST /packetcaptures/{id}/:upload.....	144
GET /packetcaptures/files.....	145
Network Scorecard.....	145
GET /network-scorecard/clientHealth/{id}.....	145
GET /network-scorecard/deviceHealth/{id}.....	145
GET /network-scorecard/networkHealth/{id}.....	145
GET /network-scorecard/serviceHealth/{id}.....	146
GET /network-scorecard/wifiHealth/{id}.....	146
Essentials - ExtremeLocation.....	146
GET /essentials/eloc/clients/{client-mac}/last-known-location.....	146
Misc - Metadata - Country.....	146
GET /countries.....	146
GET /countries/{countryAlpha2Code}/states.....	147
GET /countries/{id}/:validate.....	147
Thread.....	147
GET /thread/networks.....	147
GET /thread/routers.....	147
GET /thread/topology.....	147
NG-REPORTS (On Demand).....	148
GET /ng-reports/download/reports/:id.....	148
POST /ng-reports/download/reports/.....	148
GET /ng-reports/information.....	148
GET /ng-reports/information/:netrics.....	148
POST /ng-reports/metadata/application.....	148
POST /ng-reports/metadata/bands.....	149
POST /ng-reports/metadata/channel.....	149
POST /ng-reports/metadata/client.....	149
POST /ng-reports/metadata/device.....	149
POST /ng-reports/metadata/os.....	149
POST /ng-reports/metadata/ssids.....	150
POST /ng-reports/metadata/user.....	150
POST /ng-reports/tabledata.....	150
POST /ng-reports/timeseries.....	150
NG-REPORTS (Scheduled).....	150
GET /ng-reports/scheduled/{id}/recipients.....	151
PUT /ng-reports/scheduled/{id}/recipients.....	151

POST /ng-reports/scheduled/{id}/recipients.....	151
PATCH /ng-reports/scheduled/{id}/recipients.....	151
GET /ng-reports/scheduled/custom.....	151
POST /ng-reports/scheduled/custom.....	151
DELETE /ng-reports/scheduled/custom.....	152
GET /ng-reports/scheduled/custom/{id}.....	152
PUT /ng-reports/scheduled/custom/{id}.....	152
GET /ng-reports/scheduled/custom/{id}/runs.....	152
GET /ng-reports/scheduled/network-summary.....	152
GET /ng-reports/scheduled/pci-compliance.....	153
GET /ng-reports/scheduled/reports/download.....	153
DELETE /ng-reports/scheduled/runs.....	153
GET /ng-reports/scheduled/runs/{id}/recipients.....	153
Universal Compute Platform.....	153
GET /upc/{id}/engines/installed.....	154
AFC-endpoint.....	154
POST /afc/aps/reportFtm.....	154
POST /afc/export.....	154
POST /afc/filter-metadata.....	154
POST /afc/mobileapp/apcandidates.....	154
POST /afc/recalculateSite/{id}.....	154
GET /afc/reports/:id.....	155
GET /afc/rm-devices-page.....	155
GET /afcserver.....	155
GET /afcserver/{id}.....	155
GET /afcserver/statistics/{id}.....	155
GET /afcserver/diagnostics/{id}.....	155
GET /ap/afc/floorReport/{deviceId}.....	155
GET /ap/afc/interface/details/{sn}.....	156
POST /ap/spectrum.....	156
GET /aps/afc/query.....	156
POST /aps/afc/query.....	156
POST /aps/afc/update.....	156
GET /floor/afc/details.....	156
PUT /floor/afc/details.....	156
POST /floor/afc/details.....	157
DELETE /floor/afc/details/{id}.....	157
GET /site/afc/schedule.....	157
PUT /site/afc/schedule.....	157
POST /site/afc/schedule.....	157
POST /site/spectrum.....	157
RTTS-endpoint.....	158
POST /rtts-endpoint.....	158
POST /rtts-endpoint.....	158
AIRRM-endpoint.....	158
POST /airrm/ap/radioInfo.....	158
POST /airrm/device/{sn}.....	158
POST /airrm/radio/apInfo/:radioMac.....	158

APPENDIX – A.....159

API call list based on Roles.....159

Administrator.....	159
Operator.....	159
Monitor.....	159
Installer.....	166
Observer.....	173
Help Desk.....	180
Application Operator.....	182
Guest Management.....	182

APPENDIX – B.....184

API call list based on Permission.....184

logout.....	184
auth.....	184
auth:r.....	184
token:new.....	184
perm:check.....	184
lro.....	184
lro:r.....	184
account.....	184
account:switch.....	185
account:r.....	185
viq:backup.....	185
backup-history.....	185
viq:default-device-password.....	185
hiq.....	185
hiq:r.....	186
org.....	186
org:new.....	186
org:del.....	186
org:rename.....	186
hiq.ctx.....	186
hiq.ctx:r.....	186
hiq.ctx:w.....	186
device.....	187
device:r.....	188
device:list.....	189
device:view.....	189
device:relaxed_read.....	189
device:new.....	189
device:del.....	189
device:cli.....	190
device:deploy.....	190
device:manage.....	190
device:unmanage.....	190
device:reboot.....	190
device:reset.....	190
device:thread-commissioner.....	190
d360:relaxed_read.....	190

dashboard:relaxed_read.....	190
client.....	191
client:r.....	192
applications-reports.....	192
applications-usage.....	192
locations.....	192
locations:r.....	193
locations:floor-map-labels.....	193
network-policy.....	193
policy:ssid.....	193
network-policy:r.....	194
network-scorecard.....	194
network-scorecard:r.....	194
ssid.....	194
ssid:r.....	194
pcg:key.....	195
pcg:key:r.....	195
subscriptions-webhook.....	195
subscriptions-webhook:r.....	195
ccg.....	195
ccg:r.....	195
log.....	195
log:r.....	196
cwp.....	196
cwp:r.....	196
sms-tmpl.....	196
sms-tmpl:r.....	196
class-rule.....	196
class-rule:r.....	196
user-profile.....	196
user-profile:r.....	197
mac-object-profiles.....	197
mac-object-profiles:r.....	197
mac-firewall-policies.....	197
mac-firewall-policies:r.....	197
ip-firewall-policies.....	197
ip-firewall-policies:r.....	197
tunnel-concentrator.....	198
tunnel-concentrator:r.....	198
network-services.....	198
network-services:r.....	198
radius-proxy.....	198
radius-proxy:r.....	198
radius-server.....	198
radius-server:r.....	199
radsec-proxies.....	199
radsec-proxies:r.....	199
usergroup.....	199
usergroup:r.....	199
credential-distribution-groups.....	199
credential-distribution-groups:r.....	199

third-party-api-connection.....	199
third-party-api-connection:r.....	200
deployment.....	200
deployment:r.....	200
ad-server.....	200
ad-server:r.....	200
alert.....	200
alert:r.....	200
alert-policies.....	200
alert-policies:r.....	201
alert-subscriptions.....	201
alert-subscriptions:r.....	201
app.....	201
application:r.....	202
l3-address-profile.....	202
l3-address-profile:r.....	202
vlan-profile.....	202
vlan-profile:r.....	202
enduser.....	202
enduser:r.....	202
radius-client-object.....	203
radius-client-object:r.....	203
ldap-server.....	203
ldap-server:r.....	203
email-template.....	203
email-template:r.....	203
certificate.....	203
certificate:r.....	203
certificate-bundles.....	203
certificate-bundles:r.....	203
radio-profile.....	204
radio-profile:r.....	204
iot-profile.....	204
iot-profile:r.....	205
client-monitor-profile.....	205
client-monitor-profile:r.....	205
user-profile-assignments.....	205
user-profile-assignments:r.....	205
switch-inspector.....	205
copilot-connectivity-wired:r.....	205
copilot-connectivity-wireless:r.....	205
copilot-anomalies.....	206
copilot-anomalies:r.....	206
licenses.....	207
licenses:r.....	207
copilot-assurance-scans:r.....	207
packet-capture.....	207
packet-capture:r.....	207
country.....	207
country:r.....	208
cas.....	208

cas:r.....	208
cas-policies.....	208
cas-policies:r.....	208
cas-metadata:r.....	208
cns-subscriptions.....	208
cns-subscriptions:r.....	208
hotspot-profile.....	208
hotspot-profile:r.....	208
hotspot-service-provider-profile.....	208
hotspot-service-provider-profile:r.....	208
afc:relaxed_read.....	209
afc-filter-metadata:relaxed_read.....	209
afc-export:relaxed_read.....	209
afc-reports:relaxed_read.....	209
floor-afc-details.....	209
floor-afc-details:r.....	209
rtts.....	209
rtts:r.....	209
ng-reports.....	209
ng-reports:r.....	210
acct-api-token.....	210
acct-api-token:r.....	211
site-afc-schedule.....	211
site-afc-schedule:r.....	211
ap-spectrum.....	211
ap-spectrum:r.....	211
afc-candidates.....	211
ng-scheduled-reports:w.....	211
ng-scheduled-get-reports:r.....	211
account-user-external.....	211
account-user-me.....	212
client-user-reports.....	212
account-user-id.....	212
account-user-list.....	212
account-user-create.....	212
client-user-data-usage.....	212
client-user-filter-metadata.....	212
client-user-grid.....	212
client-user-grid-export.....	212
client-user-type-distribution.....	212
account-user-modify.....	212

Introduction

This document will list each category of XIQ APIs and all the API calls under those categories. Laid out as it is laid out on the api.extremecloudiq.com Swagger page. Under each category, the document will list the category permissions that can be used for the API calls in that category. Most categories have two permissions for the category. The first permission will match or be similar to the category's name. Example - **device** for the devices category. This permission will give access to all the GET, POST, PUT, PATCH, and DELETE API calls in that category. The second permission will be named the same as the first but followed with a *:r*. Example - **device:r** for the devices category. This permission will give access to only the GET API calls in that category.

This document will also list any additional permissions available for a particular API call. This would allow for a token to be created only to be able to perform a specific API call without having permission to do all API calls within the category. Example – **device:list** under the [GET /devices](#) API call. This would allow the token only to be able to view the list of devices using that API call but not be able to perform any of the other GET API calls in the devices category. This document also notes which Roles have access to each of the API call.

In addition, there is [Appendix - A](#) that lists the different roles with a list of the API calls available to those roles by default as well as [Appendix – B](#) that lists the different permissions with a list of the API calls available with that permission.

Authentication

No default permissions for this category

POST /login

No permissions needed – This call uses basic auth to generate a token. This token will have access to APIs based on the user's role.

POST /logout

Permissions:

"logout" – revokes currently used token

Roles:

"Operator",

"Help Desk",

"Monitor",

"Administrator",

"Installer",

"Observer",

"Guest Management"

Authorization

Permissions:

"auth" – Permission for all API calls in the Authorization Section

"auth:r" – Permission for all GET API calls in the Authorization Section

POST /auth/apitoken

Permissions:

"token:new" – Permission to generate a new token.

NOTE: new tokens can only be granted permissions that the currently used token has.

Also included with *"auth"*

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer"

POST /auth/apitoken/:validate

Permissions:

No Specific permission - included with *"auth"*

Roles:

"Operator",

"Administrator"

GET /auth/apitoken/info

Permissions:

No Specific permission - included with *"auth"* and *"auth:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

GET /auth/permissions

Permissions:

No Specific permission - included with *"auth"* and *"auth:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

POST /auth/permissions/:check

Permissions:

"perm:check" – Allows token to check permissions needed for any API call

Also included with *"auth"*

Roles

"Operator",
"Administrator"

Operation

Permissions:

"lro" – Permission for all API calls in the Operation Section

"lro:r" – Permission for all GET API calls in the Operation Section

GET /operations/{operationId}

Permissions:

No Specific permission - included with *"lro"* and *"lro:r"*

Roles:

"Operator",
"Administrator"

DELETE /operations/{operationId}

Permissions:

No Specific permission - included with *"lro"*

Roles:

"Operator",
"Administrator"

POST /operations/{operationId}/:cancel

Permissions:

No Specific permission - included with “lro”

Roles:

"Operator",

"Administrator"

Operation

Permissions:

"lro" – Permission for all API calls in the Operation Section

"lro:r" – Permission for all GET API calls in the Operation Section

GET /operations/{operation id}

Permissions:

No Specific permission - included with “lro” and “lro:r”

Roles:

"Operator",

"Help Desk",

"Administrator",

"Monitor",

"Installer",

"Observer",

"Guest Management"

DELETE /operations/{operation id}

Permissions:

No Specific permission - included with “lro”

Roles:

"Operator",

"Administrator"

POST /operations/{operation id}/:cancel

Permissions:

No Specific permission - included with “lro”

Roles:

"Operator",

"Administrator"

Account

"account" – Permission for all API calls in the Account Section

"account:r" – Permission for all GET API calls in the Account Section

POST /account/:switch

Permissions:

"account:switch" – Allows user to switch to external account

Also included with *"account"*

Roles:

**"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Application Operator",
"Guest Management"**

GET /account/external

Permissions:

No Specific permission - included with *"account"* and *"account:r"*

Roles:

**"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Application Operator",
"Guest Management"**

GET /account/home

Permissions:

No Specific permission - included with *"account"* and *"account:r"*

Roles:

**"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Application Operator",
"Guest Management"**

GET /account/third-party-applications

Permissions:

No Specific permission - included with *"account"* and *"account:r"*

Roles:

"Operator",

"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Application Operator",
"Guest Management"

GET /account/vhm/setting

Permissions:

No Specific permission - included with *"account"* and *"account:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Application Operator",
"Guest Management"

PUT /account/vhm/setting/{id}

Permissions:

No Specific permission - included with *"account"*

Roles:

"Operator",
"Administrator"

GET /account/vhm/setting/status

Permissions:

No Specific permission - included with *"account"* and *"account:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Application Operator",
"Guest Management"

GET /account/viq

Permissions:

No Specific permission - included with *"account"* and *"account:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Application Operator",
"Guest Management"

POST /account/viq/:backup

Permissions:

"viq:backup" – Permission to backup the viq.

Also included with *"account"*

Roles:

"Operator",
"Administrator"

POST /account/viq/:reset

Permissions:

No Specific permission - included with *"account"*

Roles:

"Operator",
"Administrator"

GET /account/viq/default-device-password

Permissions:

No Specific permission - included with *"account"* and *"account:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Application Operator",
"Guest Management"

PUT /account/viq/default-device-password

Permissions:

No Specific permission - included with *"account"*

Roles:

"Operator",
"Administrator"

GET /account/viq/download

Permissions:

No Specific permission - included with “*account*” and “*account:r*”

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Application Operator",
"Guest Management"

POST /account/viq/export

Permissions:

No Specific permission - included with “*account*”

Roles:

"Operator",
"Administrator"

GET /account/viq/export-import-status

Permissions:

No Specific permission - included with “*account*” and “*account:r*”

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Application Operator",
"Guest Management"

POST /account/viq/import

Permissions:

No Specific permission - included with “*account*”

Roles:

"Operator",
"Administrator"

POST /backup/history/:restore

Permissions:

“**backup-history**” – Permission for VIQ Backup and restore

Roles:

"Operator",
"Administrator"

POST /backup/history/delete

Permissions:

"backup-history" – Permission for VIQ Backup and restore

Roles:

"Operator",
"Administrator"

GET /backup/history/grid

Permissions:

NOT SET!

Roles:

NOT SET!

PUT /backup/history/grid

Permissions:

NOT SET!

Roles:

NOT SET!

Users

Permissions:

GET /users

Permissions:

"account-user-list" – Permission to get but not edit user

Roles:

"Operator",
"Administrator",
"Monitor"

POST /users

Permissions:

"account-user-create" – Permission to get and edit user but not delete

Roles:

"Administrator"

GET /users/{id}

Permissions:

"account-user-list" – Permission to get but not edit user

Roles:

"Operator",
"Administrator",
"Monitor"

DELETE /users/{id}

Permissions:

No Specific permission

Roles:

"Administrator"

PATCH /users/{id}

Permissions:

No Specific permission

Roles:

"Administrator"

POST /users/data-usage

Permissions:

"client-user-data-usage" – Permission to access user data-usage

Roles:

"Operator",

"Help Desk",

"Monitor",

"Administrator",

"Installer",

"Observer"

GET /users/external

Permissions:

"account-user-external" – Permission to get external users

Roles:

"Administrator"

POST /users/external

Permissions:

"account-user-external" – Permission to get external users

Roles:

"Administrator"

GET /users/external/{id}

Permissions:

"account-user-external" – Permission to get external users

Roles:

"Administrator"

DELETE /users/external/{id}

Permissions:

"account-user-external" – Permission to get external users

Roles:

"Administrator"

PATCH /users/external/{id}

Permissions:

"account-user-external" – Permission to get external users

Roles:

"Administrator"

POST /users/filter-metadata

Permissions:

"client-user-filter-metadata" – Permission for user filter metagdata

Roles:

"Operator",

"Help Desk",

"Monitor",

"Administrator",

"Installer",

"Observer"

POST /users/grid

Permissions:

"client-user-grid" – Permission for user grid

Roles:

"Operator",

"Help Desk",

"Monitor",

"Administrator",

"Installer",

"Observer"

POST /users/grid-export

Permissions:

"client-user-grid-export" – Permission for user grid export

Roles:

"Operator",

"Help Desk",

"Monitor",

"Administrator",

"Installer",

"Observer"

GET /users/me

Permissions:

"account-user-me:r" – Permission to view details on yourself

Roles:

"Operator",
"Help Desk",
"Monitor",
"Administrator",
"Installer",
"Observer"

GET /users/report/{id}

Permissions:

"client-user-reports" – Permission for users report by id

Roles:

"Operator",
"Help Desk",
"Monitor",
"Administrator",
"Installer",
"Observer"

POST /users/type-distribution

Permissions:

"client-user-type-distribution" – Permission for user type distribution

Roles:

"Operator",
"Help Desk",
"Monitor",
"Administrator",
"Installer",
"Observer"

Use Folder Preferences

No default permissions for this category

GET /user-folder-preferences

Permissions:

NOT SET!

Roles:

NOT SET!

POST /user-folder-preferences/:folderId

Permissions:

NOT SET!

Roles:

NOT SET!

HIQ

Permissions:

"hiq" – Permission for all API calls in the HIQ Section

"hiq:r" – Permission for all GET API calls in the HIQ Section

GET /hiq/context

Permissions:

"hiq.ctx" – Permission for control HIQ Context (HIQ account only).

"hiq.ctx:r" – Permission to read HIQ Context (HIQ account only).

Also included with *"hiq"* and *"hiq:r"*

Roles:

"Operator",

"Help Desk",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /hiq/context

Permissions:

"hiq.ctx" – Permission for control HIQ Context (HIQ account only).

"hiq.ctx:w" – Permission to switch HIQ Context (HIQ account only).

Also included with *"hiq"*

Roles:

"Operator",

"Administrator",

"Installer"

GET /hiq/context/creating

Permissions:

"hiq.ctx" – Permission for control HIQ Context (HIQ account only).

"hiq.ctx:r" – Permission to read HIQ Context (HIQ account only).

Also included with *"hiq"* and *"hiq:r"*

Roles:

"Operator",

"Help Desk",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /hiq/context/creating

Permissions:

"hiq.ctx" – Permission for full control HIQ Context (HIQ account only).

"hiq.ctx:w" – Permission to switch HIQ Context (HIQ account only).

Also included with *"hiq"*

Roles:

"Operator",
"Administrator",
"Installer"

GET /hiq/context/reading

Permissions:

"hiq.ctx" – Permission for control HIQ Context (HIQ account only).

"hiq.ctx:r" – Permission to read HIQ Context (HIQ account only).

Also included with *"hiq"* and *"hiq:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /hiq/context/reading

Permissions:

"hiq.ctx" – Permission for control HIQ Context (HIQ account only).

"hiq.ctx:w" – Permission to switch HIQ Context (HIQ account only).

Also included with *"hiq"*

Roles:

"Operator",
"Administrator",
"Installer"

GET /hiq/organizations

Permissions:

"org" – Permission for full control HIQ organizations (HIQ account only).

Also included with *"hiq"* and *"hiq:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /hiq/organizations

Permissions:

"org" – Permission for full control HIQ organizations (HIQ account only).

"org:new" – Permission to create HIQ organization (HIQ account only).

Also included with *"hiq"*

Roles:

"Operator",

"Administrator"

DELETE /hiq/organizations/{id}

Permissions:

"org" – Permission for full control HIQ organizations (HIQ account only).

"org:del" – Permission to delete HIQ organization (HIQ account only).

Also included with *"hiq"*

Roles:

"Operator",

"Administrator"

POST /hiq/organizations/{id}:/rename

Permissions:

"org" – Permission for full control HIQ organizations (HIQ account only).

"org:rename" – Permission to rename HIQ organization (HIQ account only).

Also included with *"hiq"*

Roles:

"Operator",

"Administrator"

GET /hiq/status

Permissions:

No Specific permission - included with *"hiq"* and *"hiq:r"*

Roles:

"Operator",

"Help Desk",

"Administrator",

"Monitor",

"Installer",

"Observer"

Location

Permissions:

"locations" – Permission for all API calls in the Location Section

"locations:r" – Permission for all GET API calls in the Location Section

POST /locations

Permissions:

No Specific permission - included with “*locations*”

Roles:

"Operator",

"Administrator"

"Installer"

POST /locations/:init

Permissions:

No Specific permission - included with “*locations*”

Roles:

"Operator",

"Administrator"

"Installer"

PUT /locations/{id}

Permissions:

No Specific permission - included with “*locations*”

Roles:

"Operator",

"Administrator"

"Installer"

DELETE /locations/{id}

Permissions:

No Specific permission - included with “*locations*”

Roles:

"Operator",

"Administrator"

"Installer"

GET /locations/building

Permissions:

No Specific permission - included with “*locations*” and “*locations:r*”

Roles:

"Operator",

"Help Desk",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /locations/building

Permissions:

No Specific permission - included with “*locations*”

Roles:

"Operator",

"Administrator"

"Installer"

GET /locations/building/{id}

Permissions:

No Specific permission - included with *"locations"* and *"locations:r"*

Roles:

"Operator",

"Help Desk",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /locations/building/{id}

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",

"Administrator"

"Installer"

DELETE /locations/building/{id}

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",

"Administrator"

"Installer"

GET /locations/floor

Permissions:

No Specific permission - included with *"locations"* and *"locations:r"*

Roles:

"Operator",

"Help Desk",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /locations/floor

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator"
"Installer"

GET /locations/floor/{floorId}/label

Permissions:

"locations:floor-map-labels" – Permission for floor label

Also included with "locations" and "locations:r"

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /locations/floor/{floorId}/label

Permissions:

"locations:floor-map-labels" – Permission for floor label

Also included with "locations"

Roles:

"Operator",
"Administrator"
"Installer"

POST /locations/floor/{floorId}/label

Permissions:

"locations:floor-map-labels" – Permission for floor label

Also included with "locations"

Roles:

"Operator",
"Administrator"
"Installer"

DELETE /locations/floor/{floorId}/label/{labelId}

Permissions:

"locations:floor-map-labels" – Permission for floor label

Also included with "locations"

Roles:

"Operator",
"Administrator"
"Installer"

GET /locations/floor/{id}

Permissions:

No Specific permission - included with *"locations"* and *"locations:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /locations/floor/{id}

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator"
"Installer"

DELETE /locations/floor/{id}

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator"
"Installer"

PUT /locations/floor/bulk/label

Permissions:

"locations:floor-map-labels" – Permission for floor label

Also included with *"locations"*

Roles:

"Operator",
"Administrator"
"Installer"

POST /locations/floorplan

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator"
"Installer"

GET /locations/folder/zone/{id}

Permissions:

No Specific permission - included with *"locations"* and *"locations:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

DELETE /locations/folder/zone/{id}

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator",
"Installer"

PUT /locations/folder/zone

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator",
"Installer"

POST /locations/folder/zone

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator",
"Installer"

POST /locations/import/ekahau

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator",
"Installer"

GET /locations/site

Permissions:

No Specific permission - included with *"locations"* and *"locations:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",

"Monitor",
"Installer",
"Observer"

POST /locations/site

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator"
"Installer"

GET /locations/site/{id}

Permissions:

No Specific permission - included with *"locations"* and *"locations:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /locations/site/{id}

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator"
"Installer"

DELETE /locations/site/{id}

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator"
"Installer"

GET /locations/tree

Permissions:

No Specific permission - included with *"locations"* and *"locations:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",

"Monitor",
"Installer",
"Observer"

GET /locations/tree/devices

Permissions:

No Specific permission - included with *"locations"* and *"locations:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /locations/tree/maps

Permissions:

No Specific permission - included with *"locations"* and *"locations:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /locations/wall/type

Permissions:

No Specific permission - included with *"locations"* and *"locations:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /locations/wall/type

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator",
"Installer"

PUT /locations/wall/type/{id}

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator",
"Installer"

DELETE /locations/wall/type/{id}

Permissions:

No Specific permission - included with *"locations"*

Roles:

"Operator",
"Administrator",
"Installer"

GET /locations/wall/type/references/{id}

Permissions:

No Specific permission - included with *"locations"* and *"locations:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

Device

Permissions:

"device" – Permission for all API calls in the Device Section

"device:r" – Permission for all GET API calls in the Device Section

GET /devices

Permissions:

"device:list" – Permission to get the list of devices

Also included with *"device"* and *"device:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /devices/:advanced-onboard

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/:check-ownership

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/:cli

Permissions:

“**device:cli**” – Permission to send cli commands to device(s)

Also included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/:delete

Permissions:

“**device:del**” – Permission to delete device(s)

Also included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/:manage

Permissions:

“**device:mange**” – Permission to change management on device(s) to MANAGED

Also included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/:onboard

Permissions:

“**device:new**” – Permission to onboard device(s)

Also included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/:reboot

Permissions:

“**device:reboot**” – Permission to reboot device(s)

Also included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/:reset

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/:ssh-active-sessions

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/:unmanage

Permissions:

“**device:mange**” – Permission to change management on device(s) to UNMANAGED

Also included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

GET /devices/{id}

Permissions:

“**device:view**” – Permission to view details of a device

Also included with “*device*” and “*device:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

DELETE /devices/{id}

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/{id}/:cli

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/{id}/:manage

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/{id}/:reboot

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/{id}/:reset

Permissions:

“**device:reset**” – Permission to reset a device to factory default

Also included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/{id}/:unmanage

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

GET /devices/{id}/alarms

Permissions:

No Specific permission - included with “*device*” and “*device:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /devices/{id}/bounce-port

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

GET /devices/{id}/client-monitor

Permissions:

No Specific permission - included with “*device*” and “*device:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /devices/{id}/client-monitor

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

DELETE /devices/{id}/client-monitor

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

PUT /devices/{id}/description

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

GET /devices/{id}/ftm-settings

Permissions:

No Specific permission - included with “*device*” and “*device:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /devices/{id}/config/ftm-settings

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

DELETE /devices/{id}/config/ftm-settings

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

GET /devices/{id}/gallery-image

Permissions:

No Specific permission - included with “*device*” and “*device:r*”

Roles:

"Operator",
"Administrator",

**"Monitor",
"Installer",
"Observer"**

GET /devices/{id}/geolocation

Permissions:

No Specific permission - included with *"device"* and *"device:r"*

Roles:

**"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"**

GET /devices/{id}/history/cpu-mem

Permissions:

No Specific permission - included with *"device"* and *"device:r"*

Roles:

**"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"**

PUT /devices/{id}/hostname

Permissions:

No Specific permission - included with *"device"*

Roles:

**"Operator",
"Administrator",
"Installer"**

GET /devices/{id}/ibeacon

Permissions:

No Specific permission - included with *"device"* and *"device:r"*

Roles:

**"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"**

GET /devices/{id}/installation-report

Permissions:

No Specific permission - included with *"device"* and *"device:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /devices/{id}/interfaces/wifi

Permissions:

No Specific permission - included with *"device"* and *"device:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /devices/{id}/iot

Permissions:

No Specific permission - included with *"device"* and *"device:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /devices/{id}/iot/:disable

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/{id}/iot/:enable

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

GET /devices/{id}/location

Permissions:

No Specific permission - included with *"device"* and *"device:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /devices/{id}/location

Permissions:

No Specific permission - included with "*device*"

Roles:

"Operator",
"Administrator",
"Installer"

DELETE /devices/{id}/location

Permissions:

No Specific permission - included with "*device*"

Roles:

"Operator",
"Administrator",
"Installer"

PUT /devices/{id}/mobileapp/gps

Permissions:

No Specific permission - included with "*device*"

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/{id}/monitor/:refresh

Permissions:

No Specific permission - included with "*device*"

Roles:

"Operator",
"Administrator",
"Installer"

GET /devices/{id}/monitor/refresh/status

Permissions:

No Specific permission - included with "*device*" and "*device:r*"

Roles:

"Operator",
"Administrator",
"Monitor",

"Installer",
"Observer"

GET /devices/{id}/network-policy

Permissions:

No Specific permission - included with *"device"* and *"device:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /devices/{id}/network-policy

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

DELETE /devices/{id}/network-policy

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

GET /devices/{id}/radio-operating-mode

Permissions:

No Specific permission - included with *"device"* and *"device:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /devices/{id}/radio-operating-mode

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/{id}/ssid/:override

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

GET /devices/{id}/ssid/status

Permissions:

No Specific permission - included with “*device*” and “*device:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /devices/{id}/ssid/status/:change

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/{id}/thread/commissioner/:start

Permissions:

“*device:thread-commissioner*” – Permission to change thread commissioner to device(s)

Also included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/{id}/thread/commissioner/:stop

Permissions:

“*device:thread-commissioner*” – Permission to change thread commissioner to device(s)

Also included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

PUT /devices/{id}/thread/visible

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/actions-support-metadata

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/anchor/assign

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/anchor/revoke

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/client-monitor/:assign

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/ client-monitor/:revoke

Permissions:

No Specific permission - included with “*device*”

Roles:

"Operator",
"Administrator",

"Installer"

POST /devices/client-monitor/:query

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/country-code/:assign

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

GET /devices/{id}/digital-twin

Permissions:

"device:view" – Permission to view details of a device

Also included with *"device"* and *"device:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /devices/ibeacon

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/location/:assign

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",

"Installer"

POST /devices/location/:query

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/location/:revoke

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/network-policy/:assign

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/network-policy/:query

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/network-policy/:revoke

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

GET /devices/network-policy/{policyId}

Permissions:

No Specific permission - included with *"device"* and *"device:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /devices/os/:change

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

GET /devices/radio-information

Permissions:

"device:list" – Permission to get the list of devices

Also included with *"device"* and *"device:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /devices/radius-proxy/:assign

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

DELETE /devices/radius-proxy/:revoke

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

GET /devices/reports/{id}

Permissions:

No Specific permission - included with *"device"* and *"device:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /devices/rm-devices-connection-status

Permissions:

"device:relaxed_read" – Permission to read using the POST call

Also included with "device"

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /devices/rm-devices-metadata

Permissions:

"device:relaxed_read" – Permission to read using the POST call

Also included with "device"

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /devices/rm-devices-page

Permissions:

"device:relaxed_read" – Permission to read using the POST call

Also included with "device"

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /devices/rm-devices-page/export

Permissions:

"device:relaxed_read" – Permission to read using the POST call

Also included with "device"

Roles:

"Operator",

"Administrator",
"Monitor",
"Installer",
"Observer"

GET /devices/rm-devices-stack/{id}

Permissions:

No Specific permission - included with *"device"* and *"device:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /devices/stats

Permissions:

"device:view" – Permission to view details of a device

Also included with *"device"* and *"device:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /devices/thread/commissioner/start

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

POST /devices/thread/commissioner/stop

Permissions:

No Specific permission - included with *"device"*

Roles:

"Operator",
"Administrator",
"Installer"

Network Policy

Permissions:

"network-policy" – Permission for all API calls in the Network Policy Section

"network-policy:r" – Permission for all GET API calls in the Network Policy Section

GET /network-policies

Permissions:

No Specific permission - included with *"network-policy"* and *"network-policy:r"*

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /network-policies

Permissions:

No Specific permission - included with *"network-policy"*

Roles:

"Operator",

"Administrator"

GET /network-policies/{id}

Permissions:

No Specific permission - included with *"network-policy"* and *"network-policy:r"*

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /network-policies/{id}

Permissions:

No Specific permission - included with *"network-policy"*

Roles:

"Operator",

"Administrator"

DELETE /network-policies/{id}

Permissions:

No Specific permission - included with *"network-policy"*

Roles:

"Operator",

"Administrator"

GET /network-policies/{id}/ssids

Permissions:

No Specific permission - included with “*network-policy*” and “*network-policy:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /network-policies/{id}/ssids/:add

Permissions:

"policy:ssid" – SSID management on network-policy

Also included with “*network-policy*”

Roles:

"Operator",
"Administrator"

POST /network-policies/{id}/ssids/:remove

Permissions:

"policy:ssid" – SSID management on network-policy

Also included with “*network-policy*”

Roles:

"Operator",
"Administrator"

Client

Permissions:

"client" – Permission for all API calls in the Client Section

"client:r" – Permission for all GET API calls in the Client Section

GET /clients/{id}

Permissions:

No Specific permission - included with “*client*” and “*client:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /clients/active

Permissions:

No Specific permission - included with “*client*” and “*client:r*”

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /clients/alias

Permissions:

No Specific permission - included with “*client*”

Roles:

"Operator",
"Administrator"

GET /clients/active/count

Permissions:

No Specific permission - included with “*client*” and “*client:r*”

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /clients/byMac/{client_mac}

Permissions:

No Specific permission - included with “*client*” and “*client:r*”

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

DELETE /clients/byMac/{client_mac}

Permissions:

No Specific permission - included with “*client*”

Roles:

"Operator",
"Administrator"

POST /clients/disconnect

Permissions:

No Specific permission - included with “client”

Roles:

"Operator",

"Administrator"

GET /clients/summary

Permissions:

No Specific permission - included with “client” and “client:r”

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

GET /clients/usage

Permissions:

No Specific permission - included with “client” and “client:r”

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

Client - Details

No default permissions for this category

GET /client-details/client-trail/connectivity-experience/{id}

Permissions:

NOT SET!

Roles:

NOT SET!

GET /client-details/client-trail/roaming-trail/count/{id}

Permissions:

NOT SET!

Roles:

NOT SET!

GET /client-details/client-trail/roaming-trail/grid/{id}

Permissions:

NOT SET!

Roles:
NOT SET!

GET /client-details/overview/chart-data/{id}

Permissions:
NOT SET!
Roles:
NOT SET!

GET /client-details/overview/info/{id}

Permissions:
NOT SET!
Roles:
NOT SET!

GET /client-details/topology/client-trail/{client_mac}

Permissions:
NOT SET!
Roles:
NOT SET!

Switch Inspector Panel

Permissions:
"switch-inspector" – Permission for all API calls in the Switch Inspector Panel Section

POST /switch-inspector/diagnostics

Permissions:
No Specific permission - included with "switch-inspector"
Roles:
"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Guest Management"

D360

Permissions:
"d360:relaxed_read" – Permission for all API calls in the D360 Section

POST /d360/client/graph

Permissions:
No Specific permission - included with "d360:relaxed_read"
Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /d360/client/grid

Permissions:

No Specific permission - included with *"d360:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /d360/client/grid/metadata

Permissions:

NOT SET!

Roles:

NOT SET!

POST /d360/client/stats

Permissions:

NOT SET!

Roles:

NOT SET!

POST /d360/device/interfaces

Permissions:

NOT SET!

Roles:

NOT SET!

POST /d360/device/issues

Permissions:

NOT SET!

Roles:

NOT SET!

POST /d360/device/metadata

Permissions:

NOT SET!

Roles:

NOT SET!

POST /d360/device/stats

Permissions:

NOT SET!

Roles:

NOT SET!

POST /d360/event/graph

Permissions:

NOT SET!

Roles:

NOT SET!

POST /d360/overview/devices-summary

Permissions:

NOT SET!

Roles:

NOT SET!

POST /d360/ssid-metadata

Permissions:

NOT SET!

Roles:

NOT SET!

POST /d360/wired/queue-grid

Permissions:

NOT SET!

Roles:

NOT SET!

POST /d360/wireless/interfaces-graph

Permissions:

NOT SET!

Roles:

NOT SET!

POST /d360/wireless/interfaces-stats

Permissions:

NOT SET!

Roles:

NOT SET!

POST /d360/wireless/surrounding-aps

Permissions:

No Specific permission - included with “*d360:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

Dashboard

Permissions:

"dashboard:relaxed_read" – Permission for all API calls in the Dashboard Section

POST /dashboard/alerts

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/assets

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/clients

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /dashboard/device-types

Permissions:

NOT SET!

Roles:

NOT SET!

POST /dashboard/devices

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/export

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /dashboard/reports/{id}

Permissions:

NOT SET!

Roles:

NOT SET!

POST /dashboard/sites-with-issues

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/usage-capacity

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",

"Observer"

GET /dashboard/wireless/dashboard/criteria

Permissions:

NOT SET!

Roles:

NOT SET!

POST /dashboard/wireless/dashboard/criteria

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

Dashboard Wired Usage and Capacity

"dashboard:relaxed_read" – Permission for all API calls in the Dashboard Section

POST /dashboard/wired/usage-capacity/grid

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /dashboard/wired/usage-capacity/usage-utilization

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /dashboard/wired/usage-capacity/wired-congestion

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/usage-capacity/wired-throughput

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

Dashboard Wired Client Health

"dashboard:relaxed_read" – Permission for all API calls in the Dashboard Section

POST /dashboard/wired/client-health/grid

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/client-health/ip-connectivity-issues

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer"

POST /dashboard/wired/client-health/port-congestion

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",

"Installer",
"Observer"

POST /dashboard/wired/client-health/port-errors

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/client-health/traffic-anomalies

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

Dashboard Wired Device Health

"dashboard:relaxed_read" – Permission for all API calls in the Dashboard Section

POST /dashboard/wired/device-health/cpu-usage-issues

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/device-health/fan-issues

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/device-health/fan-status

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/device-health/grid

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/device-health/memory-usage-issues

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/device-health/poe-usage-issues

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/device-health/poe-usage-status

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",

"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/device-health/psu-issues

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/device-health/psu-status

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/device-health/summary

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/device-health/temperature-issues

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wired/device-health/temperature-status

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

Dashboard Wireless Usage and Capacity

"**dashboard:relaxed_read**" – Permission for all API calls in the Dashboard Section

POST /dashboard/wireless/usage-capacity/excessive-packet-loss

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/usage-capacity/excessive-retries

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/usage-capacity/excessive-utilization

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/usage-capacity/export

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/usage-capacity/grid

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /dashboard/wireless/usage-capacity/reports/{id}

Permissions:

NOT SET!

Roles:

NOT SET!

Dashboard Wireless Client Health

"dashboard:relaxed_read" – Permission for all API calls in the Dashboard Section

POST /dashboard/wireless/client-health/connectivity-issues

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/client-health/export

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/client-health/filter-metadata

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/client-health/frequency-distribution

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/client-health/grid

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/client-health/issue/association

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/client-health/issue/authentication

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",

"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/client-health/issue/ipaddress

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/client-health/issue/roaming

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /dashboard/wireless/client-health/reports/{id}

Permissions:

NOT SET!

Roles:

NOT SET!

POST /dashboard/wireless/client-health/roaming-issues

Permissions:

No Specific permission - included with *"dashboard:relaxed_read"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

Dashboard Wireless Device Health

No default permissions for this category

POST /dashboard/wireless/device-health/export

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/device-health/grid

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/device-health/cpu-usage-issues

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/device-health/memory-usage-issues

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /dashboard/wireless/device-health/poe-usage-issues

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",

“Observer”

GET /dashboard/wireless/device-health/reports/{id}

Permissions:

NOT SET!

Roles:

NOT SET!

GET /dashboard/wireless/device-health/reboot/summary

Permissions:

NOT SET!

Roles:

NOT SET!

POST /dashboard/wireless/device-health/summary

Permissions:

No Specific permission - included with “*dashboard:relaxed_read*”

Roles:

“Operator”,

“Administrator”,

“Monitor”,

“Installer”,

“Observer”

Geo View

No default permissions for this category

GET /geo-view

Permissions:

NOT SET!

Roles:

NOT SET!

Application

Permissions:

“app” – Permission for all API calls in the Application Section

“application:r” – Permission for all GET API calls in the Application Section

GET /applications

Permissions:

No Specific permission - included with “app” and “application:r”

Roles:

“Operator”,

“Administrator”,

"Monitor",
"Observer"

GET /applications/{id}/clients/top{n}

Permissions:

No Specific permission - included with *"app"* and *"application:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

GET /applications/reports/{id}

Permissions:

"applications-reports" – Permission for application reports.

Also included with *"app"* and *"application:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /applications/top{n}

Permissions:

No Specific permission - included with *"app"* and *"application:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

POST /applications/usage/summary

Permissions:

"applications-usage" – Permission for application usage.

Also included with *"app"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",

“Observer”

POST /applications/usage/summary/export

Permissions:

“**applications-usage**” – Permission for application usage.

Also included with “*app*”

Roles:

“Operator”,
“Help Desk”,
“Administrator”,
“Monitor”,
“Installer”,
“Observer”

GET /applications/usage/summary/meta-data

Permissions:

“**applications-usage**” – Permission for application usage.

Also included with “*app*” and “*application:r*”

Roles:

“Operator”,
“Help Desk”,
“Administrator”,
“Monitor”,
“Installer”,
“Observer”

Alert

No default permissions for this category

GET /alert-policies

Permissions:

“**alert-policies**” – Permission for full control of alert policies.

“**alert-policies:r**” – Permission to read alert policies.

Roles:

“Operator”,
“Administrator”,
“Monitor”,
“Installer”,
“Observer”

POST /alert-policies

Permissions:

“**alert-policies**” – Permission for full control of alert policies.

Roles:

"Operator",
"Administrator"

GET /alert-policies/{id}

Permissions:

"alert-policies" – Permission for full control of alert policies.

"alert-policies:r" – Permission to read alert policies.

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /alert-policies/{id}

Permissions:

"alert-policies" – Permission for full control of alert policies.

Roles:

"Operator",
"Administrator"

DELETE /alert-policies/{id}

Permissions:

"alert-policies" – Permission for full control of alert policies.

Roles:

"Operator",
"Administrator"

GET /alert-policies/{id}/rules/{alert_rule_id}

Permissions:

"alert-policies" – Permission for full control of alert policies.

"alert-policies:r" – Permission to read alert policies.

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /alert-policies/{id}/rules/{alert_rule_id}

Permissions:

"alert-policies" – Permission for full control of alert policies.

Roles:

"Operator",
"Administrator"

POST /alert-policies/{id}/rules/{alert_rule_id}/:disable

Permissions:

"alert-policies" – Permission for full control of alert policies.

Roles:

"Operator",
"Administrator"

PUT /alert-policies/{id}/rules/{alert_rule_id}/:enable

Permissions:

"alert-policies" – Permission for full control of alert policies.

Roles:

"Operator",
"Administrator"

GET /alert-policies/available-sites

Permissions:

"alert-policies" – Permission for full control of alert policies.

"alert-policies:r" – Permission to read alert policies.

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /alert-subscriptions/emails

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

"alert-subscriptions:r" – Permission to read alert subscriptions.

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /alert-subscriptions/emails

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

Roles:

"Operator",
"Administrator"

POST /alert-subscriptions/emails/:delete

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

Roles:

"Operator",
"Administrator"

GET /alert-subscriptions/emails/{id}

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

"alert-subscriptions:r" – Permission to read alert subscriptions.

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /alert-subscriptions/emails/{id}

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

Roles:

"Operator",
"Administrator"

DELETE /alert-subscriptions/emails/{id}

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

Roles:

"Operator",
"Administrator"

POST /alert-subscriptions/emails/{id}:verify

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

Roles:

"Operator",
"Administrator"

GET /alert-subscriptions/servicenow

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

"alert-subscriptions:r" – Permission to read alert subscriptions.

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /alert-subscriptions/servicenow

Permissions:

"**alert-subscriptions**" – Permission for full control of alert subscriptions.

Roles:

"Operator",
"Administrator"

POST /alert-subscriptions/servicenow/:delete

Permissions:

"**alert-subscriptions**" – Permission for full control of alert subscriptions.

Roles:

"Operator",
"Administrator"

GET /alert-subscriptions/servicenow/{id}

Permissions:

"**alert-subscriptions**" – Permission for full control of alert subscriptions.

"**alert-subscriptions:r**" – Permission to read alert subscriptions.

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /alert-subscriptions/servicenow/{id}

Permissions:

"**alert-subscriptions**" – Permission for full control of alert subscriptions.

Roles:

"Operator",
"Administrator"

PATCH /alert-subscriptions/servicenow/{id}

Permissions:

"**alert-subscriptions**" – Permission for full control of alert subscriptions.

Roles:

"Operator",
"Administrator"

GET /alert-subscriptions/webhooks

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

"alert-subscriptions:r" – Permission to read alert subscriptions.

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /alert-subscriptions/webhooks

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

Roles:

"Operator",

"Administrator"

POST /alert-subscriptions/webhooks/:delete

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

Roles:

"Operator",

"Administrator"

GET /alert-subscriptions/webhooks/{id}

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

"alert-subscriptions:r" – Permission to read alert subscriptions.

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /alert-subscriptions/webhooks/{id}

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

Roles:

"Operator",

"Administrator"

DELETE /alert-subscriptions/webhooks/{id}

Permissions:

"alert-subscriptions" – Permission for full control of alert subscriptions.

Roles:

"Operator",

"Administrator"

GET /alerts

Permissions:

"alert" – Permission for full control of alerts.

"alert:r" – Permission to read alerts.

Roles:

"Operator",

"Help Desk",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /alerts/:acknowledge

Permissions:

"alert" – Permission for full control of alert subscriptions.

Roles:

"Operator",

"Administrator"

GET /alerts/count-by-{group}

Permissions:

"alert" – Permission for full control of alerts.

"alert:r" – Permission to read alerts.

Roles:

"Operator",

"Help Desk",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /alerts/report

Permissions:

"alert" – Permission for full control of alert subscriptions.

Roles:

"Operator",

"Administrator"

GET /alerts/reports/{id}

Permissions:

"alert" – Permission for full control of alerts.

"alert:r" – Permission to read alerts.

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

Log

Permissions:

"log" – Permission for all API calls in the Log Section

"log:r" – Permission for all GET API calls in the Log Section

GET /logs/accounting

Permissions:

No Specific permission - included with *"log"* and *"log:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
'Installer',
"Observer",
"Application Operator"

GET /logs/audit

Permissions:

No Specific permission - included with *"log"* and *"log:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
'Installer',
"Observer",
"Application Operator"

GET /logs/audit/full-descriptions/{id}

Permissions:

No Specific permission - included with *"log"* and *"log:r"*

Roles:

"Operator",
"Administrator",
"Monitor",

'Installer',
"Observer",
"Application Operator"

POST /logs/audit/reports

Permissions:

No Specific permission - included with "log"

Roles:

"Operator",
"Administrator"

GET /logs/audit/reports/{id}

Permissions:

No Specific permission - included with "log" and "log:r"

Roles:

"Operator",
"Administrator",
"Monitor",
'Installer',
"Observer",
"Application Operator"

GET /logs/auth

Permissions:

No Specific permission - included with "log" and "log:r"

Roles:

"Operator",
"Administrator",
"Monitor",
'Installer',
"Observer",
"Application Operator"

GET /logs/credential

Permissions:

No Specific permission - included with "log" and "log:r"

Roles:

"Operator",
"Administrator",
"Monitor",
'Installer',
"Observer",
"Application Operator"

GET /logs/email

Permissions:

No Specific permission - included with “log” and “log:r”

Roles:

"Operator",
"Administrator",
"Monitor",
'Installer',
"Observer",
"Application Operator"

GET /logs/sms

Permissions:

No Specific permission - included with “log” and “log:r”

Roles:

"Operator",
"Administrator",
"Monitor",
'Installer',
"Observer",
"Application Operator"

Notification

Permissions:

" **subscriptions-webhook**" – Permission for all API calls in the Notification Section

" **subscriptions-webhook:r**" – Permission for all GET API calls in the Notification Section

GET /subscriptions/webhook

Permissions:

No Specific permission - included with “subscriptions-webhook” and “subscriptions-webhook:r”

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

POST /subscriptions/webhook

Permissions:

No Specific permission - included with “subscriptions-webhook”

Roles:

"Operator",
"Administrator"

DELETE /subscriptions/webhook/:delete

Permissions:

No Specific permission - included with “*subscriptions-webhook*”

Roles:

"Operator",
"Administrator"

PUT /subscriptions/webhook/{id}

Permissions:

No Specific permission - included with “*subscriptions-webhook*”

Roles:

"Operator",
"Administrator"

GET /subscriptions/webhook/export

Permissions:

No Specific permission - included with “*subscriptions-webhook*” and “*subscriptions-webhook:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

Administration

No default permissions for this category

GET /acct-api-token

Permissions:

“**acct-api-token**” – Permission for full access to Legacy API tokens

“**acct-api-token:r**” – Permission to read Legacy API tokens

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /acct-api-token

Permissions:

“**acct-api-token**” – Permission for full access to Legacy API tokens

Roles:

"Operator",
"Administrator"

DELETE /acct-api-token/:delete

Permissions:

"acct-api-token" – Permission for full access to Legacy API tokens

Roles:

"Operator",

"Administrator"

DELETE /acct-api-token/{id}

Permissions:

"acct-api-token" – Permission for full access to Legacy API tokens

Roles:

"Operator",

"Administrator"

PATCH /acct-api-token/{id}

Permissions:

"acct-api-token" – Permission for full access to Legacy API tokens

Roles:

"Operator",

"Administrator"

GET /acct-api-token/export

Permissions:

"acct-api-token" – Permission for full access to Legacy API tokens

"acct-api-token:r" – Permission to read Legacy API tokens

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

GET /credential-distribution-groups

Permissions:

"credential-distribution-groups" – Permission for full access to credential distribution groups

"credential-distribution-groups:r" – Permission to read credential distribution groups

Roles:

"Operator",

"Administrator",

"Monitor",

"Observer",

"Guest Management"

POST /credential-distribution-groups

Permissions:

"credential-distribution-groups" – Permission for full access to credential distribution groups

Roles:

"Operator",
"Administrator"

DELETE /credential-distribution-groups

Permissions:

"credential-distribution-groups" – Permission for full access to credential distribution groups

Roles:

"Operator",
"Administrator"

PUT /credential-distribution-groups/{id}

Permissions:

"credential-distribution-groups" – Permission for full access to credential distribution groups

Roles:

"Operator",
"Administrator"

GET /third-party-api-connection

Permissions:

"third-party-api-connection" – Permission for full access to third party API connection

"third-party-api-connection:r" – Permission to read third party API connection

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer",
"Guest Management"

PUT /third-party-api-connection

Permissions:

"third-party-api-connection" – Permission for full access to third party API connection

Roles:

"Operator",
"Administrator"

DELETE /third-party-api-connection

Permissions:

"third-party-api-connection" – Permission for full access to third party API connection

Roles:

"Operator",
"Administrator"

NOS

No default permissions for this category

Configuration - Deployment

Permissions:

"**deployment**" – Permission for all API calls in the Configuration - Deployment Section

"**deployment:r**" – Permission for all GET API calls in the Configuration – Deployment Section

GET /deployments

Permissions:

No Specific permission - included with "*deployment*" and "*deployment:r*"

Roles:

"Operator",

"Help Desk",

"Administrator",

"Monitor",

"Installer",

"Observer",

"Guest Management"

POST /deployments

Permissions:

No Specific permission - included with "*deployment*"

Roles:

"Operator",

"Administrator"

GET /deployments/{id}

Permissions:

No Specific permission - included with "*deployment*" and "*deployment:r*"

Roles:

"Operator",

"Help Desk",

"Administrator",

"Monitor",

"Installer",

"Observer",

"Guest Management"

PUT /deployments/{id}

Permissions:

No Specific permission - included with "*deployment*"

Roles:

"Operator",
"Administrator"

DELETE /deployments/{id}

Permissions:

No Specific permission - included with *"deployment"*

Roles:

"Operator",
"Administrator"

GET /deployments/{id}/status

Permissions:

No Specific permission - included with *"deployment"* and *"deployment:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Guest Management"

POST /deployments/firmware-metadatas

Permissions:

No Specific permission - included with *"deployment"*

Roles:

"Operator",
"Administrator"

GET /deployments/overview

Permissions:

No Specific permission - included with *"deployment"* and *"deployment:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Guest Management"

GET /deployments/status

Permissions:

No Specific permission - included with *"deployment"* and *"deployment:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer",
"Guest Management"

Configuration - Basic

Permissions:

"vlan-profile" – Permission for all API calls in the Configuration - Basic Section

"vlan-profile:r" – Permission for all GET API calls in the Configuration – Basic Section

GET /vlan-profiles

Permissions:

No Specific permission - included with *"vlan-profile"* and *"vlan-profile:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

POST /vlan-profiles

Permissions:

No Specific permission - included with *"vlan-profile"*

Roles:

"Operator",
"Administrator"

POST /vlan-profiles/:delete

Permissions:

No Specific permission - included with *"vlan-profile"*

Roles:

"Operator",
"Administrator"

GET /vlan-profiles/{id}

Permissions:

No Specific permission - included with *"vlan-profile"* and *"vlan-profile:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

DELETE /vlan-profiles/{id}

Permissions:

No Specific permission - included with “vlan-profile”

Roles:

"Operator",

"Administrator"

PATCH /vlan-profiles/{id}

Permissions:

No Specific permission - included with “vlan-profile”

Roles:

"Operator",

"Administrator"

Configuration - User Management

No default permissions for this category

GET /email-templates

Permissions:

“email-template” – Permission for full of email template.

“email-template:r” – Permission to read email templates

Roles:

"Operator",

"Administrator",

"Monitor",

“Observer”

GET /endusers

Permissions:

“enduser” – Permission for full control of end users.

“enduser:r” – Permission to read end users

Roles:

"Operator",

“Help Desk”,

"Administrator",

"Monitor",

“Observer”,

“Guest Management”

POST /endusers

Permissions:

“enduser” – Permission for full control of end users.

Roles:

"Operator",
"Administrator",
"Guest Management"

PUT /endusers/{id}

Permissions:

"enduser" – Permission for full control of end users.

Roles:

"Operator",
"Administrator",
"Guest Management"

DELETE /endusers/{id}

Permissions:

"enduser" – Permission for full control of end users.

Roles:

"Operator",
"Administrator",
"Guest Management"

POST /endusers/{id}/:regenerate-password

Permissions:

"enduser" – Permission for full control of end users.

Roles:

"Operator",
"Administrator",
"Guest Management"

GET /pcgs/key-based

Permissions:

"pcg:key" – Permission for full control of PCG key based.

"pcg:key:r" – Permission to read PCG key based

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

POST /pcgs/key-based

Permissions:

"pcg:key" – Permission for full control of PCG key based.

Roles:

"Operator",
"Administrator"

DELETE /pcgs/key-based/network-policy-{policyId}

Permissions:

"pcg:key" – Permission for full control of PCG key based.

Roles:

"Operator",

"Administrator"

POST /pcgs/key-based/network-policy-{policyId}/:onboard

Permissions:

"pcg:key" – Permission for full control of PCG key based.

Roles:

"Operator",

"Administrator"

POST /pcgs/key-based/network-policy-{policyId}/keys/:email

Permissions:

"pcg:key" – Permission for full control of PCG key based.

Roles:

"Operator",

"Administrator"

POST /pcgs/key-based/network-policy-{policyId}/keys/:generate

Permissions:

"pcg:key" – Permission for full control of PCG key based.

Roles:

"Operator",

"Administrator"

GET /pcgs/key-based/network-policy-{policyId}/port-assignments

Permissions:

"pcg:key" – Permission for full control of PCG key based.

"pcg:key:r" – Permission to read PCG key based

Roles:

"Operator",

"Administrator",

"Monitor",

"Observer"

POST /pcgs/key-based/network-policy-{policyId}/port-assignments

Permissions:

"pcg:key" – Permission for full control of PCG key based.

Roles:

"Operator",

"Administrator"

GET /pcgs/key-based/network-policy-{policyId}/users

Permissions:

"pcg:key" – Permission for full control of PCG key based.

"pcg:key:r" – Permission to read PCG key based

Roles:

"Operator",

"Administrator",

"Monitor",

"Observer"

PUT /pcgs/key-based/network-policy-{policyId}/users

Permissions:

"pcg:key" – Permission for full control of PCG key based.

Roles:

"Operator",

"Administrator"

POST /pcgs/key-based/network-policy-{policyId}/users

Permissions:

"pcg:key" – Permission for full control of PCG key based.

Roles:

"Operator",

"Administrator"

DELETE /pcgs/key-based/network-policy-{policyId}/users

Permissions:

"pcg:key" – Permission for full control of PCG key based.

Roles:

"Operator",

"Administrator"

GET /sms-templates

Permissions:

"sms-tmpl" – Permission for full control of SMS template.

"sms-tmpl:r" – Permission to read SMS template

Roles:

"Operator",

"Administrator",

"Monitor",

"Observer"

GET /usergroups

Permissions:

"usergroup" – Permission for full control of user groups.

"usergroup:r" – Permission to read user groups

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer",
"Guest Management"

POST /usergroups

Permissions:

"usergroup" – Permission for full control of user groups.

Roles:

"Operator",
"Administrator"

GET /usergroups/:unique

Permissions:

"usergroup" – Permission for full control of user groups.

"usergroup:r" – Permission to read user groups

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer",
"Guest Management"

PUT /usergroups/{id}

Permissions:

"usergroup" – Permission for full control of user groups.

Roles:

"Operator",
"Administrator"

DELETE /usergroups/{id}

Permissions:

"usergroup" – Permission for full control of user groups.

Roles:

"Operator",
"Administrator"

Configuration - Policy

No default permissions for this category

GET /ccgs

Permissions:

"ccg" – Permission for full control of CCG.

"ccg:r" – Permission to read CCG

Roles:

"Operator",

"Administrator",

"Monitor",

"Observer"

POST /ccgs

Permissions:

"ccg" – Permission for full control of CCG.

Roles:

"Operator",

"Administrator"

GET /ccgs/{id}

Permissions:

"ccg" – Permission for full control of CCG.

"ccg:r" – Permission to read CCG

Roles:

"Operator",

"Administrator",

"Monitor",

"Observer"

PUT /ccgs/{id}

Permissions:

"ccg" – Permission for full control of CCG.

Roles:

"Operator",

"Administrator"

DELETE /ccgs/{id}

Permissions:

"ccg" – Permission for full control of CCG.

Roles:

"Operator",

"Administrator"

GET /classification-rules

Permissions:

"class-rule" – Permission for full control of classification rule.

"class-rule:r" – Permission to read classification rule

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

POST /classification-rules

Permissions:

"class-rule" – Permission for full control of classification rule.

Roles:

"Operator",
"Administrator"

GET /classification-rules/{id}

Permissions:

"class-rule" – Permission for full control of classification rule.

"class-rule:r" – Permission to read classification rule

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

PUT /classification-rules/{id}

Permissions:

"class-rule" – Permission for full control of classification rule.

Roles:

"Operator",
"Administrator"

DELETE /classification-rules/{id}

Permissions:

"class-rule" – Permission for full control of classification rule.

Roles:

"Operator",
"Administrator"

GET /client-monitor-profiles

Permissions:

"client-monitor-profile" – Permission for full control of client monitor profiles

"client-monitor-profile:r" – Permission to read client monitor profiles

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer",
"Installer"

POST /client-monitor-profile

Permissions:

"client-monitor-profile" – Permission for full control of client monitor profiles

Roles:

"Operator",
"Administrator"

GET /client-monitor-profile/{id}

Permissions:

"client-monitor-profile" – Permission for full control of client monitor profiles

"client-monitor-profile:r" – Permission to read client monitor profiles

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer",
"Installer"

PUT /client-monitor-profile/{id}

Permissions:

"client-monitor-profile" – Permission for full control of client monitor profiles

Roles:

"Operator",
"Administrator"

DELETE /client-monitor-profile/{id}

Permissions:

"client-monitor-profile" – Permission for full control of client monitor profiles

Roles:

"Operator",
"Administrator"

GET /hotspot-profiles

Permissions:

"hotspot-profile" – Permission for full control of hotspot-profiles.

"hotspot-profile:r" – Permission to read hotspot-profiles.

Roles:

"Operator",
"Administrator",

"Monitor",
"Installer",
"Observer"

POST /hotspot-profiles

Permissions:

"hotspot-profile" – Permission for full control of hotspot-profiles.

Roles:

"Operator",
"Administrator"

GET /hotspot-profiles/{id}

Permissions:

"hotspot-profile" – Permission for full control of hotspot-profiles.

"hotspot-profile:r" – Permission to read hotspot-profiles.

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /hotspot-profiles/{id}

Permissions:

"hotspot-profile" – Permission for full control of hotspot-profiles.

Roles:

"Operator",
"Administrator"

DELETE /hotspot-profiles/{id}

Permissions:

"hotspot-profile" – Permission for full control of hotspot-profiles.

Roles:

"Operator",
"Administrator"

GET /hotspot-service-provider-profiles

Permissions:

"hotspot-service-provider-profile" – Permission for full control of hotspot-service-provider-profiles.

"hotspot-service-provider-profile:r" – Permission to read hotspot-service-provider-profiles.

Roles:

"Operator",
"Administrator",
"Monitor",

"Installer",
"Observer"

POST /hotspot-service-provider-profiles

Permissions:

"hotspot-service-provider-profile" – Permission for full control of hotspot-service-provider-profiles.

Roles:

"Operator",
"Administrator"

GET /hotspot-service-provider-profiles/{id}

Permissions:

"hotspot-service-provider-profile" – Permission for full control of hotspot-service-provider-profiles.

"hotspot-service-provider-profile:r" – Permission to read hotspot-service-provider-profiles.

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /hotspot-service-provider-profiles/{id}

Permissions:

"hotspot-service-provider-profile" – Permission for full control of hotspot-service-provider-profiles.

Roles:

"Operator",
"Administrator"

DELETE /hotspot-service-provider-profiles/{id}

Permissions:

"hotspot-service-provider-profile" – Permission for full control of hotspot-service-provider-profiles.

Roles:

"Operator",
"Administrator"

GET /iot-profiles

Permissions:

"iot-profile" – Permission for full control of iot-profiles.

"iot-profile:r" – Permission to read iot-profiles.

Roles:

"Operator",

"Administrator",
"Monitor",
"Installer",
"Observer"

POST /iot-profiles

Permissions:

"**iot-profile**" – Permission for full control of iot-profiles.

Roles:

"Operator",
"Administrator"

GET /iot-profiles/{id}

Permissions:

"**iot-profile**" – Permission for full control of iot-profiles.

"**iot-profile:r**" – Permission to read iot-profiles.

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /iot-profiles/{id}

Permissions:

"**iot-profile**" – Permission for full control of iot-profiles.

Roles:

"Operator",
"Administrator"

DELETE /iot-profiles/{id}

Permissions:

"**iot-profile**" – Permission for full control of iot-profiles.

Roles:

"Operator",
"Administrator"

GET /ip-firewall-policies

Permissions:

"**ip-firewall-policies**" – Permission for full control of IP firewall policies.

"**ip-firewall-policies:r**" – Permission to read IP firewall policies.

Roles:

"Operator",
"Administrator",

"Monitor",
"Installer",
"Observer"

POST /ip-firewall-policies

Permissions:

"ip-firewall-policies" – Permission for full control of IP firewall policies.

Roles:

"Operator",
"Administrator"

GET /ip-firewall-policies/{id}

Permissions:

"ip-firewall-policies" – Permission for full control of IP firewall policies.

"ip-firewall-policies:r" – Permission to read IP firewall policies.

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /ip-firewall-policies/{id}

Permissions:

"ip-firewall-policies" – Permission for full control of IP firewall policies.

Roles:

"Operator",
"Administrator"

DELETE /ip-firewall-policies/{id}

Permissions:

"ip-firewall-policies" – Permission for full control of IP firewall policies.

Roles:

"Operator",
"Administrator"

POST /ip-firewall-policies/{id}/attach

Permissions:

"ip-firewall-policies" – Permission for full control of IP firewall policies.

Roles:

"Operator",
"Administrator"

POST /ip-firewall-policies/{id}/detach

Permissions:

"ip-firewall-policies" – Permission for full control of IP firewall policies.

Roles:

"Operator",

"Administrator"

GET /l3-address-profiles

Permissions:

"l3-address-profile" – Permission for full control of L3 address profile.

"l3-address-profile:r" – Permission to read L3 address profile

Roles:

"Operator",

"Administrator",

"Monitor",

"Observer"

POST /l3-address-profiles

Permissions:

"l3-address-profile" – Permission for full control of L3 address profile.

Roles:

"Operator",

"Administrator"

GET /l3-address-profiles/{id}

Permissions:

"l3-address-profile" – Permission for full control of L3 address profile.

"l3-address-profile:r" – Permission to read L3 address profile

Roles:

"Operator",

"Administrator",

"Monitor",

"Observer"

PUT /l3-address-profiles/{id}

Permissions:

"l3-address-profile" – Permission for full control of L3 address profile.

Roles:

"Operator",

"Administrator"

DELETE /l3-address-profiles/{id}

Permissions:

"l3-address-profile" – Permission for full control of L3 address profile.

Roles:

"Operator",

"Administrator"

GET /mac-firewall-policies

Permissions:

"mac-firewall-policies" – Permission for full control of MAC firewall policies.

"mac-firewall-policies:r" – Permission to read MAC firewall policies.

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /mac-firewall-policies

Permissions:

"mac-firewall-policies" – Permission for full control of MAC firewall policies.

Roles:

"Operator",

"Administrator"

GET /mac-firewall-policies/{id}

Permissions:

"mac-firewall-policies" – Permission for full control of MAC firewall policies.

"mac-firewall-policies:r" – Permission to read MAC firewall policies.

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /mac-firewall-policies/{id}

Permissions:

"mac-firewall-policies" – Permission for full control of MAC firewall policies.

Roles:

"Operator",

"Administrator"

DELETE /mac-firewall-policies/{id}

Permissions:

"mac-firewall-policies" – Permission for full control of MAC firewall policies.

Roles:

"Operator",

"Administrator"

POST /mac-firewall-policies/{id}/:attach

Permissions:

"mac-firewall-policies" – Permission for full control of MAC firewall policies.

Roles:

"Operator",

"Administrator"

POST /mac-firewall-policies/{id}/:detach

Permissions:

"mac-firewall-policies" – Permission for full control of MAC firewall policies.

Roles:

"Operator",

"Administrator"

GET /mac-object-profiles

Permissions:

"mac-object-profiles" – Permission for full control of MAC object profiles.

"mac-object-profiles:r" – Permission to read MAC object profiles.

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /mac-object-profiles

Permissions:

"mac-object-profiles" – Permission for full control of MAC object profiles.

Roles:

"Operator",

"Administrator"

GET /mac-object-profiles/{id}

Permissions:

"mac-object-profiles" – Permission for full control of MAC object profiles.

"mac-object-profiles:r" – Permission to read MAC object profiles.

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /mac-object-profiles/{id}

Permissions:

"mac-object-profiles" – Permission for full control of MAC object profiles.

Roles:

"Operator",

"Administrator"

DELETE /mac-object-profiles/{id}

Permissions:

"mac-object-profiles" – Permission for full control of MAC object profiles.

Roles:

"Operator",

"Administrator"

GET /radio-operating-modes/{id}

Permissions:

NOT SET!

Roles:

NOT SET!

GET /radio-profiles

Permissions:

"radio-profile" – Permission for full control of radio profiles

"radio-profile:r" – Permission to read radio profiles

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /radio-profiles

Permissions:

"radio-profile" – Permission for full control of radio profiles

Roles:

"Operator",

"Administrator"

GET /radio-profiles/{id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

"radio-profile:r" – Permission to read radio profiles

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /radio-profiles/{id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

Roles:

"Operator",

"Administrator",

DELETE /radio-profiles/{id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

Roles:

"Operator",

"Administrator"

GET /radio-profiles/channel-selection/{channel-selection-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

"radio-profile:r" – Permission to read radio profiles

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /radio-profiles/channel-selection/{channel-selection-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

Roles:

"Operator",

"Administrator"

GET /radio-profiles/mac-ouis

Permissions:

"radio-profile" – Permission for full control of radio profiles

"radio-profile:r" – Permission to read radio profiles

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /radio-profiles/mac-ouis

Permissions:

"radio-profile" – Permission for full control of radio profiles

Roles:

"Operator",

"Administrator"

GET /radio-profiles/mac-ouis/{mac-oui-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

"radio-profile:r" – Permission to read radio profiles

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /radio-profiles/mac-ouis/{mac-oui-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

Roles:

"Operator",

"Administrator"

DELETE /radio-profiles/mac-ouis/{mac-oui-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

Roles:

"Operator",

"Administrator"

GET /radio-profiles/miscellaneous/{radio-misc-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

"radio-profile:r" – Permission to read radio profiles

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /radio-profiles/miscellaneous/{radio-misc-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

Roles:

"Operator",

"Administrator"

GET /radio-profiles/neighborhood-analysis/{neigh-analysis-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

"radio-profile:r" – Permission to read radio profiles

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /radio-profiles/neighborhood-analysis/{neigh-analysis-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

Roles:

"Operator",

"Administrator"

GET /radio-profiles/radio-usage-opt/{radio-usage-opt-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

"radio-profile:r" – Permission to read radio profiles

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /radio-profiles/radio-usage-opt/{radio-usage-opt-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

Roles:

"Operator",

"Administrator"

GET /radio-profiles/sensor-scan/{sensor-scan-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

"radio-profile:r" – Permission to read radio profiles

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /radio-profiles/sensor-scan/{sensor-scan-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

Roles:

"Operator",

"Administrator"

GET /radio-profiles/wmm-qos/{radio-qos-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

"radio-profile:r" – Permission to read radio profiles

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /radio-profiles/wmm-qos/{radio-qos-id}

Permissions:

"radio-profile" – Permission for full control of radio profiles

Roles:

"Operator",

"Administrator"

GET /ssids

Permissions:

"ssid" – Permission for full control of SSID

"ssid:r" – Permission to read SSID

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /ssids/{id}/:rename

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",

"Administrator"

POST /ssids/{id}/client-monitor-profile/:attach

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",

"Administrator"

POST /ssids/{id}/cwp/:attach

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",

"Administrator"

POST /ssids/{id}/cwp/:disable

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",

"Administrator"

POST /ssids/{id}/cwp/:enable

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",

"Administrator"

PUT /ssids/{id}/mode/dot1x

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",

"Administrator"

PUT /ssids/{id}/mode/open

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",

"Administrator"

PUT /ssids/{id}/mode/ppsk

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",

"Administrator"

PUT /ssids/{id}/mode/psk

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",

"Administrator"

PUT /ssids/{id}/mode/wep

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",

"Administrator"

PUT /ssids/{id}/psk/password

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",

"Administrator"

POST /ssids/{id}/radius-client-profile

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",

"Administrator"

POST /ssids/{id}/radius-server-group/:attach

Attach radius server group to an SSID

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",
"Administrator"

POST /ssids/{id}/user-profile-assignment

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",
"Administrator"

POST /ssids/{id}/user-profile/:attach

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",
"Administrator"

GET /ssids/advanced-settings/{id}

Permissions:

"ssid" – Permission for full control of SSID

"ssid:r" – Permission to read SSID

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /ssids/advanced-settings/{id}

Permissions:

"ssid" – Permission for full control of SSID

Roles:

"Operator",
"Administrator"

GET /user-profile-assignments

Permissions:

"user-profile-assignments" – Permission for full control of user profile assignments

"user-profile-assignments:r" – Permission to read user profile assignments

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /user-profile-assignments

Permissions:

"user-profile-assignments" – Permission for full control of user profile assignments

Roles:

"Operator",

"Administrator"

GET /user-profile-assignments/{id}

Permissions:

"user-profile-assignments" – Permission for full control of user profile assignments

"user-profile-assignments:r" – Permission to read user profile assignments

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

DELETE /user-profile-assignments/{id}

Permissions:

"user-profile-assignments" – Permission for full control of user profile assignments

Roles:

"Operator",

"Administrator"

GET /user-profiles

Permissions:

"user-profile" – Permission for full control of user profile

"user-profile:r" – Permission to read user profile

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /user-profiles

Permissions:

"user-profile" – Permission for full control of user profile

Roles:

"Operator",

"Administrator"

GET /user-profiles/{id}

Permissions:

"user-profile" – Permission for full control of user profile

"user-profile:r" – Permission to read user profile

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /user-profiles/{id}

Permissions:

"user-profile" – Permission for full control of user profile

Roles:

"Operator",

"Administrator"

DELETE /user-profiles/{id}

Permissions:

"user-profile" – Permission for full control of user profile

Roles:

"Operator",

"Administrator"

POST /user-profiles/{id}/ip-firewall-policies/:attach

Permissions:

"user-profile" – Permission for full control of user profile

Roles:

"Operator",

"Administrator"

POST /user-profiles/{id}/ip-firewall-policies/:detach

Permissions:

"user-profile" – Permission for full control of user profile

Roles:

"Operator",

"Administrator"

POST /user-profiles/{id}/mac-firewall-policies/:attach

Permissions:

"user-profile" – Permission for full control of user profile

Roles:

"Operator",

"Administrator"

POST /user-profiles/{id}/ac-firewall-policies/:detach

Permissions:

"user-profile" – Permission for full control of user profile

Roles:

"Operator",

"Administrator"

Configuration - Network

No default permissions for this category

GET /network-services

Permissions:

"network-services" – Permission for full control of network services

"network-services:r" – Permission to read network services

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /network-services

Permissions:

"network-services" – Permission for full control of network services

Roles:

"Operator",

"Administrator"

DELETE /network-services/{id}

Permissions:

"network-services" – Permission for full control of network services

Roles:

"Operator",

"Administrator"

GET /tunnel-concentrators

Permissions:

"tunnel-concentrator" – Permission for full control of tunnel concentrator

"tunnel-concentrator:r" – Permission to read tunnel concentrator

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",
"Observer"

POST /tunnel-concentrators

Permissions:

"tunnel-concentrator" – Permission for full control of tunnel concentrator

Roles:

"Operator",
"Administrator"

GET /tunnel-concentrators/{id}

Permissions:

"tunnel-concentrator" – Permission for full control of tunnel concentrator

"tunnel-concentrator:r" – Permission to read tunnel concentrator

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /tunnel-concentrators/{id}

Permissions:

"tunnel-concentrator" – Permission for full control of tunnel concentrator

Roles:

"Operator",
"Administrator"

DELETE /tunnel-concentrators/{id}

Permissions:

"tunnel-concentrator" – Permission for full control of tunnel concentrator

Roles:

"Operator",
"Administrator"

Configuration - Authentication

No default permissions for this category

GET /ad-servers

Permissions:

"ad-server" – Permission for full control of AD server

"ad-server:r" – Permission to read AD server

Roles:

"Operator",

"Administrator",
"Monitor",
"Observer"

GET /cwps

Permissions:

"cwp" – Permission for full control of captive web portals

"cwp:r" – Permission to read captive web portals

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

GET /ldap-servers

Permissions:

"ldap-server" – Permission for full control of LDAP server

"ldap-server:r" – Permission to read LDAP server

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

POST /ldap-servers

Permissions:

"ldap-server" – Permission for full control of LDAP server

Roles:

"Operator",
"Administrator"

GET /ldap-servers/{id}

Permissions:

"ldap-server" – Permission for full control of LDAP server

"ldap-server:r" – Permission to read LDAP server

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"

PUT /ldap-servers/{id}

Permissions:

"ldap-server" – Permission for full control of LDAP server

Roles:

"Operator",
"Administrator"

DELETE /ldap-servers/{id}

Permissions:

"ldap-server" – Permission for full control of LDAP server

Roles:

"Operator",
"Administrator"

GET /radius-client-objects

Permissions:

"radius-client-object" – Permission for full control of RADIUS client object

"radius-client-object:r" – Permission to read RADIUS client object

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /radius-client-objects

Permissions:

"radius-client-object" – Permission for full control of RADIUS client object

Roles:

"Operator",
"Administrator"

GET /radius-client-objects/{id}

Permissions:

"radius-client-object" – Permission for full control of RADIUS client object

"radius-client-object:r" – Permission to read RADIUS client object

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /radius-client-objects/{id}

Permissions:

"radius-client-object" – Permission for full control of RADIUS client object

Roles:

"Operator",

"Administrator"

DELETE /radius-client-objects/{id}

Permissions:

"radius-client-object" – Permission for full control of RADIUS client object

Roles:

"Operator",

"Administrator"

GET /radius-proxies

Permissions:

"radius-proxy" – Permission for full control of RADIUS proxy

"radius-proxy:r" – Permission to read RADIUS proxy

Roles:

"Operator",

"Administrator",

"Monitor",

"Observer"

POST /radius-proxies

Permissions:

"radius-proxy" – Permission for full control of RADIUS proxy

Roles:

"Operator",

"Administrator"

GET /radius-proxies/{id}

Permissions:

"radius-proxy" – Permission for full control of RADIUS proxy

"radius-proxy:r" – Permission to read RADIUS proxy

Roles:

"Operator",

"Administrator",

"Monitor",

"Observer"

PUT /radius-proxies/{id}

Permissions:

"radius-proxy" – Permission for full control of RADIUS proxy

Roles:

"Operator",

"Administrator"

DELETE /radius-proxies/{id}

Permissions:

"radius-proxy" – Permission for full control of RADIUS proxy

Roles:

"Operator",

"Administrator"

GET /radius-proxies/devices

Permissions:

"radius-proxy" – Permission for full control of RADIUS proxy

"radius-proxy:r" – Permission to read RADIUS proxy

Roles:

"Operator",

"Administrator",

"Monitor",

"Observer"

GET /radius-servers/external

Permissions:

"radius-server" – Permission for full control of RADIUS server

"radius-server:r" – Permission to read RADIUS server

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /radius-servers/external

Permissions:

"radius-server" – Permission for full control of RADIUS server

Roles:

"Operator",

"Administrator"

GET /radius-servers/external/{id}

Permissions:

"radius-server" – Permission for full control of RADIUS server

"radius-server:r" – Permission to read RADIUS server

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /radius-servers/external/{id}

Permissions:

"radius-server" – Permission for full control of RADIUS server

Roles:

"Operator",

"Administrator"

DELETE /radius-servers/external/{id}

Permissions:

"radius-server" – Permission for full control of RADIUS server

Roles:

"Operator",

"Administrator"

GET /radius-servers/internal

Permissions:

"radius-server" – Permission for full control of RADIUS server

"radius-server:r" – Permission to read RADIUS server

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /radius-servers/internal

Permissions:

"radius-server" – Permission for full control of RADIUS server

Roles:

"Operator",

"Administrator"

DELETE /radius-servers/internal

Permissions:

"radius-server" – Permission for full control of RADIUS server

Roles:

"Operator",

"Administrator"

GET /radius-servers/internal/{id}

Permissions:

"radius-server" – Permission for full control of RADIUS server

"radius-server:r" – Permission to read RADIUS server

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /radius-servers/internal/{id}

Permissions:

"radius-server" – Permission for full control of RADIUS server

Roles:

"Operator",
"Administrator"

DELETE /radius-servers/internal/{id}

Permissions:

"radius-server" – Permission for full control of RADIUS server

Roles:

"Operator",
"Administrator"

GET /radius-servers/internal/devices

Permissions:

"radius-server" – Permission for full control of RADIUS server

"radius-server:r" – Permission to read RADIUS server

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /radsec-proxies

Permissions:

"radsec-proxy" – Permission for full control of RADSEC proxy

"radsec-proxy:r" – Permission to read RADSEC proxy

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /radsec-proxies

Permissions:

"radsec-proxy" – Permission for full control of RADSEC proxy

Roles:

"Operator",

"Administrator"

GET /radsec-proxies/{id}

Permissions:

"radsec-proxy" – Permission for full control of RADSEC proxy

"radsec-proxy:r" – Permission to read RADSEC proxy

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /radsec-proxies/{id}

Permissions:

"radsec-proxy" – Permission for full control of RADSEC proxy

Roles:

"Operator",

"Administrator"

DELETE /radsec-proxies/{id}

Permissions:

"radsec-proxy" – Permission for full control of RADSEC proxy

Roles:

"Operator",

"Administrator"

Configuration - Certificate

Permissions:

" certificate" – Permission for all API calls in the Configuration - Certificate Section

" certificate:r" – Permission for all GET API calls in the Configuration – Certificate Section

GET /certificate-bundle

Permissions:

"certificate-bundles" – Permission for full control of certificate bundles

"certificate-bundles:r" – Permission to read certificate bundles

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

POST /certificate-bundle

Permissions:

"certificate-bundles" – Permission for full control of certificate bundles

Roles:

"Operator",

"Administrator"

GET /certificate-bundle/{id}

Permissions:

"certificate-bundles" – Permission for full control of certificate bundles

"certificate-bundles:r" – Permission to read certificate bundles

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /certificate-bundle/{id}

Permissions:

"certificate-bundles" – Permission for full control of certificate bundles

Roles:

"Operator",

"Administrator"

DELETE /certificate-bundle/{id}

Permissions:

"certificate-bundles" – Permission for full control of certificate bundles

Roles:

"Operator",

"Administrator"

GET /certificates

Permissions:

No Specific permission - included with *"certificate"* and *"certificate:r"*

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

DELETE /certificates/{id}

Permissions:

No Specific permission - included with “*certificate*”

Roles:

"Operator",

"Administrator"

POST /certificates/import

Permissions:

No Specific permission - included with “*certificate*”

Roles:

"Operator",

"Administrator"

Copilot – Connectivity Experience

No default permissions for this category

GET /copilot/connectivity/client-type

Permissions:

NOT SET!

Roles:

NOT SET!

GET /copilot/connectivity/locations

Permissions:

NOT SET!

Roles:

NOT SET!

GET /copilot/connectivity/wired/events

Permissions:

“copilot-connectivity-wired:r” – Permission to read copilot wired connectivity

Roles:

"Operator",

"Monitor",

"Administrator",

"Observer",

"Guest Management"

GET /copilot/connectivity/wired/experience

Permissions:

“copilot-connectivity-wired:r” – Permission to read copilot wired connectivity

Roles:

"Operator",

"Monitor",

"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wired/hardware

Permissions:

"copilot-connectivity-wired:r" – Permission to read copilot wired connectivity

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wired/locations/hardware

Permissions:

"copilot-connectivity-wired:r" – Permission to read copilot wired connectivity

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wired/quality-index

Permissions:

"copilot-connectivity-wired:r" – Permission to read copilot wired connectivity

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wireless/apps

Permissions:

"copilot-connectivity-wireless:r" – Permission to read copilot wireless connectivity

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wireless/events

Permissions:

"copilot-connectivity-wireless:r" – Permission to read copilot wireless connectivity

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wireless/experience

Permissions:

"copilot-connectivity-wireless:r" – Permission to read copilot wireless connectivity

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wireless/locations/events

Permissions:

"copilot-connectivity-wireless:r" – Permission to read copilot wireless connectivity

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wireless/locations/performance

Permissions:

"copilot-connectivity-wireless:r" – Permission to read copilot wireless connectivity

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wireless/locations/quality-index

Permissions:

"copilot-connectivity-wireless:r" – Permission to read copilot wireless connectivity

Roles:

"Operator",

"Monitor",
"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wireless/locations/time-to-connect

Permissions:

"copilot-connectivity-wireless:r" – Permission to read copilot wireless connectivity

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wireless/performance

Permissions:

"copilot-connectivity-wireless:r" – Permission to read copilot wireless connectivity

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wireless/quality-index

Permissions:

"copilot-connectivity-wireless:r" – Permission to read copilot wireless connectivity

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wireless/time-to-connect

Permissions:

"copilot-connectivity-wireless:r" – Permission to read copilot wireless connectivity

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

GET /copilot/connectivity/wireless/views

Permissions:

"copilot-connectivity-wireless:r" – Permission to read copilot wireless connectivity

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

Copilot – Anomalies

Permissions:

"copilot-anomalies" – Permission for full control in the Copilot Anomalies Section

"copilot-anomalies:r" – Permission for all read Copilot Anomalies Section

GET /copilot/anomalies/adverse-traffic/device-stats

Permissions:

No Specific permission - included with *"copilot-anomalies"* and *"copilot-anomalies:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET / copilot/anomalies/adverse-traffic/packet-counts

Permissions:

No Specific permission - included with *"copilot-anomalies"* and *"copilot-anomalies:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET /copilot/anomalies/anomalies-by-category

Permissions:

No Specific permission - included with *"copilot-anomalies"* and *"copilot-anomalies:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET /copilot/anomalies/device-by-location

Permissions:

No Specific permission - included with “*copilot-anomalies*” and “*copilot-anomalies:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET /copilot/anomalies/device-with-locations

Permissions:

No Specific permission - included with “*copilot-anomalies*” and “*copilot-anomalies:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

PUT /copilot/anomalies/devices/feedback

Permissions:

No Specific permission - included with “*copilot-anomalies*”

Roles:

"Operator",
"Administrator"

PUT /copilot/anomalies/devices/update-action

Permissions:

No Specific permission - included with “*copilot-anomalies*”

Roles:

"Operator",
"Administrator"

GET /copilot/anomalies/dfs-recurrence/channel-stats

Permissions:

No Specific permission - included with “*copilot-anomalies*” and “*copilot-anomalies:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET /copilot/anomalies/dfs-recurrence/count-stats

Permissions:

No Specific permission - included with “*copilot-anomalies*” and “*copilot-anomalies:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

POST /copilot/anomalies/exclude-vlans

Permissions:

No Specific permission - included with “*copilot-anomalies*”

Roles:

"Operator",
"Administrator"

POST /copilot/anomalies/exclude-vlans-csv

Permissions:

No Specific permission - included with “*copilot-anomalies*”

Roles:

"Operator",
"Administrator"

GET /copilot/anomalies/exclude-vlans-list

Permissions:

No Specific permission - included with “*copilot-anomalies*”

Roles:

"Operator",
"Administrator"

GET /copilot/anomalies/hardware-health/client-list

Permissions:

No Specific permission - included with “*copilot-anomalies*” and “*copilot-anomalies:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET /copilot/anomalies/hardware-health/cpu-mem-stats

Permissions:

No Specific permission - included with “*copilot-anomalies*” and “*copilot-anomalies:r*”

Roles:

"Operator",

**"Administrator",
"Monitor",
"Observer"
"Guest Management"**

GET /copilot/anomalies/hardware-health/stats

Permissions:

No Specific permission - included with *"copilot-anomalies"* and *"copilot-anomalies:r"*

Roles:

**"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"**

GET /copilot/anomalies/locations

Permissions:

No Specific permission - included with *"copilot-anomalies"* and *"copilot-anomalies:r"*

Roles:

**"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"**

GET /copilot/anomalies/missing-vlan/count

Permissions:

No Specific permission - included with *"copilot-anomalies"* and *"copilot-anomalies:r"*

Roles:

**"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"**

GET /copilot/anomalies/notifications

Permissions:

No Specific permission - included with *"copilot-anomalies"* and *"copilot-anomalies:r"*

Roles:

**"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"**

GET /copilot/anomalies/poeflapping/lldp-cdp-info

Permissions:

No Specific permission - included with “*copilot-anomalies*” and “*copilot-anomalies:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET /copilot/anomalies/poeflapping/stats

Permissions:

No Specific permission - included with “*copilot-anomalies*” and “*copilot-anomalies:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET /copilot/anomalies/poeflapping/trends

Permissions:

No Specific permission - included with “*copilot-anomalies*” and “*copilot-anomalies:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET /copilot/anomalies/port-efficiency/speed-duplex-stats

Permissions:

No Specific permission - included with “*copilot-anomalies*” and “*copilot-anomalies:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET /copilot/anomalies/port-efficiency/stats

Permissions:

No Specific permission - included with “*copilot-anomalies*” and “*copilot-anomalies:r*”

Roles:

"Operator",
"Administrator",

"Monitor",
"Observer"
"Guest Management"

GET /copilot/anomalies/wifi-capacity/client-list

Permissions:

No Specific permission - included with "*copilot-anomalies*" and "*copilot-anomalies:r*"

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET /copilot/anomalies/wifi-capacity/stats

Permissions:

No Specific permission - included with "*copilot-anomalies*" and "*copilot-anomalies:r*"

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET /copilot/anomalies/report

Permissions:

No Specific permission - included with "*copilot-anomalies*" and "*copilot-anomalies:r*"

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

PUT /copilot/anomalies/update-action

Permissions:

No Specific permission - included with "*copilot-anomalies*"

Roles:

"Operator",
"Administrator"

PUT / copilot/anomalies/update-device-action

Permissions:

No Specific permission - included with "*copilot-anomalies*"

Roles:

"Operator",

"Administrator"

GET /copilot/anomalies/wifi-efficiency/client-list

Permissions:

No Specific permission - included with *"copilot-anomalies"* and *"copilot-anomalies:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET /copilot/anomalies/wifi-efficiency/stats

Permissions:

No Specific permission - included with *"copilot-anomalies"* and *"copilot-anomalies:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Observer"
"Guest Management"

GET /copilot/assurance-scans/overview

Permissions:

"copilot-assurance-scans:r" – Permission to read access to Copilot Assurance scan

Roles:

"Operator",
"Monitor",
"Administrator",
"Observer",
"Guest Management"

Packet Capture

Permissions:

"packet-capture " – Permission for all API calls in the Packet Capture Section

"packet-capture:r" – Permission for all GET API calls in the Packet Capture Section

GET /packetcaptures

Permissions:

No Specific permission - included with *"packet-capture"* and *"packet-capture:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",

"Installer"
"Observer"

POST /packetcaptures

Permissions:

No Specific permission - included with *"packet-capture"*

Roles:

"Operator",
"Help Desk",
"Administrator"

DELETE /packetcaptures

Permissions:

No Specific permission - included with *"packet-capture"*

Roles:

"Operator",
"Help Desk",
"Administrator"

GET /packetcaptures/{id}

Permissions:

No Specific permission - included with *"packet-capture"* and *"packet-capture:r"*

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer"
"Observer"

Delete /packetcaptures/{id}

Permissions:

No Specific permission - included with *"packet-capture"*

Roles:

"Operator",
"Help Desk",
"Administrator"

POST /packetcaptures/{id}/:stop

Permissions:

No Specific permission - included with *"packet-capture"*

Roles:

"Operator",
"Help Desk",
"Administrator"

POST /packetcaptures/{id}/:upload

Permissions:

No Specific permission - included with “*packet-capture*”

Roles:

"Operator",
"Help Desk",
"Administrator"

GET /packetcaptures/files

Permissions:

No Specific permission - included with “*packet-capture*” and “*packet-capture:r*”

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer"
"Observer"

Network Scorecard

Permissions:

"network-scorecard " – Permission for all API calls in the Network Scorecard Section

"network-scorecard:r" – Permission for all GET API calls in the Network Scorecard Section

GET /network-scorecard/clientHealth/{id}

Permissions:

No Specific permission - included with “*network-scorecard*” and “*network-scorecard:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /network-scorecard/deviceHealth/{id}

Permissions:

No Specific permission - included with “*network-scorecard*” and “*network-scorecard:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /network-scorecard/networkHealth/{id}

Permissions:

No Specific permission - included with “*network-scorecard*” and “*network-scorecard:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /network-scorecard/serviceHealth/{id}

Permissions:

No Specific permission - included with “*network-scorecard*” and “*network-scorecard:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /network-scorecard/wifiHealth/{id}

Permissions:

No Specific permission - included with “*network-scorecard*” and “*network-scorecard:r*”

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

Essentials - ExtremeLocation

No default permissions for this category

GET /essentials/eloc/clients/{client-mac}/last-known-location

Permissions:

NOT SET!

Roles:

NOT SET!

Misc - Metadata - Country

Permissions:

"country " – Permission for all API calls in the Metadata-Country Section

"country:r" – Permission for all GET API calls in the Metadata-Country Section

GET /countries

Permissions:

No Specific permission - included with “country” and “country:r”

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /countries/{countryAlpha2Code}/states

Permissions:

No Specific permission - included with “country” and “country:r”

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /countries/{id}/:validate

Permissions:

No Specific permission - included with “country” and “country:r”

Roles:

"Operator",
"Help Desk",
"Administrator",
"Monitor",
"Installer",
"Observer"

Thread

No default permissions for this category

GET /thread/networks

Permissions:

NOT SET!

Roles:

NOT SET!

GET /thread/routers

Permissions:

NOT SET!

Roles:
NOT SET!

GET /thread/topology

Permissions:
NOT SET!
Roles:
NOT SET!

NG-REPORTS (On Demand)

Permissions:
"ng-reports" – Permission for all API calls in the NG-Reports Section
"ng-reports:r" – Permission for all GET API calls in the NG-Reports Section

GET /ng-reports/download/reports/:id

Permissions:
No Specific permission - included with "ng-reports" and "ng-reports:r"
Roles:
"Operator",
"Administrator",
"Monitor",
"Installer"

POST /ng-reports/download/reports/

Permissions:
No Specific permission - included with "ng-reports" and "ng-reports:r"
Roles:
"Operator",
"Administrator",
"Monitor",
"Installer"

GET /ng-reports/information

Permissions:
No Specific permission - included with "ng-reports" and "ng-reports:r"
Roles:
"Operator",
"Administrator",
"Monitor",
"Installer"

GET /ng-reports/information/:netrics

Permissions:
No Specific permission - included with "ng-reports" and "ng-reports:r"
Roles:

"Operator",
"Administrator",
"Monitor",
"Installer"

POST /ng-reports/metadata/application

Permissions:

No Specific permission - included with *"ng-reports"* and *"ng-reports:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer"

POST /ng-reports/metadata/bands

Permissions:

No Specific permission - included with *"ng-reports"* and *"ng-reports:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer"

POST /ng-reports/metadata/channel

Permissions:

No Specific permission - included with *"ng-reports"* and *"ng-reports:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer"

POST /ng-reports/metadata/client

Permissions:

No Specific permission - included with *"ng-reports"* and *"ng-reports:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer"

POST /ng-reports/metadata/device

Permissions:

No Specific permission - included with *"ng-reports"* and *"ng-reports:r"*

Roles:

"Operator",

"Administrator",
"Monitor",
"Installer"

POST /ng-reports/metadata/os

Permissions:

No Specific permission - included with *"ng-reports"* and *"ng-reports:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer"

POST /ng-reports/metadata/ssids

Permissions:

No Specific permission - included with *"ng-reports"* and *"ng-reports:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer"

POST /ng-reports/metadata/user

Permissions:

No Specific permission - included with *"ng-reports"* and *"ng-reports:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer"

POST /ng-reports/tabledata

Permissions:

No Specific permission - included with *"ng-reports"* and *"ng-reports:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer"

POST /ng-reports/timeseries

Permissions:

No Specific permission - included with *"ng-reports"* and *"ng-reports:r"*

Roles:

"Operator",
"Administrator",

"Monitor",
"Installer"

NG-REPORTS (Scheduled)

Permissions:

"ng-reports" – Permission for all API calls in the NG-Reports Section

"ng-reports:r" – Permission for all GET API calls in the NG-Reports Section

GET /ng-reports/scheduled/{id}/recipients

"ng-scheduled-reports:r" – Permission to read scheduled NG-Reports

Also included with "ng-reports" and "ng-reports:r"

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /ng-reports/scheduled/{id}/recipients

"ng-scheduled-reports:w" – Permission to update a scheduled NG-Reports

Also included with "ng-reports"

Roles:

"Operator",
"Administrator"

POST /ng-reports/scheduled/{id}/recipients

"ng-scheduled-reports:w" – Permission to create a scheduled NG-Reports

Also included with "ng-reports" and "ng-reports:r"

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer"

PATCH /ng-reports/scheduled/{id}/recipients

"ng-scheduled-reports:w" – Permission to update a scheduled NG-Reports

Also included with "ng-reports"

Roles:

"Operator",
"Administrator"

GET /ng-reports/scheduled/custom

"ng-scheduled-reports:r" – Permission to read scheduled NG-Reports

Also included with "ng-reports" and "ng-reports:r"

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /ng-reports/scheduled/custom

"ng-scheduled-reports:w" – Permission to create a scheduled NG-Reports

Also included with *"ng-reports"* and *"ng-reports:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer"

DELETE /ng-reports/scheduled/custom

"ng-scheduled-reports:w" – Permission to update a scheduled NG-Reports

Also included with *"ng-reports"*

Roles:

"Operator",
"Administrator"

GET /ng-reports/scheduled/custom/{id}

"ng-scheduled-reports:r" – Permission to read scheduled NG-Reports

Also included with *"ng-reports"* and *"ng-reports:r"*

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

PUT /ng-reports/scheduled/custom/{id}

"ng-scheduled-reports:w" – Permission to update a scheduled NG-Reports

Also included with *"ng-reports"*

Roles:

"Operator",
"Administrator"

GET /ng-reports/scheduled/custom/{id}/runs

"ng-scheduled-reports:r" – Permission to read scheduled NG-Reports

Also included with *"ng-reports"* and *"ng-reports:r"*

Roles:

"Operator",

"Administrator",
"Monitor",
"Installer",
"Observer"

GET /ng-reports/scheduled/network-summary

"ng-scheduled-reports:r" – Permission to read scheduled NG-Reports

Also included with "ng-reports" and "ng-reports:r"

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /ng-reports/scheduled/pci-compliance

"ng-scheduled-reports:r" – Permission to read scheduled NG-Reports

Also included with "ng-reports" and "ng-reports:r"

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

GET /ng-reports/scheduled/reports/download

"ng-scheduled-reports:r" – Permission to read scheduled NG-Reports

Also included with "ng-reports" and "ng-reports:r"

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

DELETE /ng-reports/scheduled/runs

"ng-scheduled-reports:w" – Permission to read scheduled NG-Reports

Also included with "ng-reports"

Roles:

"Operator",
"Administrator"

GET /ng-reports/scheduled/runs/{id}/recipients

"ng-scheduled-reports:r" – Permission to read scheduled NG-Reports

Also included with "ng-reports" and "ng-reports:r"

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

Universal Compute Platform

No default permissions for this category

GET /upc/{id}/engines/installed

Permissions:

NOT SET!

Roles:

NOT SET!

AFC-endpoint

No default permissions for this category

POST /afc/aps/reportFtm

Permissions:

NOT SET!

Roles:

NOT SET!

POST /afc/export

Permissions:

"afc-export:relaxed_read" – Permission to read afc export

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /afc/filter-metadata

Permissions:

"afc-filtr-metadata:relaxed_read" – Permission to read filter metadata

Roles:

"Operator",
"Administrator",
"Monitor",
"Installer",
"Observer"

POST /afc/mobileapp/apcandidates

Permissions:

“afc-candidates” – Permission to set AFC candidates

Roles:

"Operator",

"Administrator"

POST /afc/recalculateSite/{id}

Permissions:

NOT SET!

Roles:

NOT SET!

GET /afc/reports/:id

Permissions:

NOT SET!

Roles:

NOT SET!

GET /afc/rm-devices-page

Permissions:

NOT SET!

Roles:

NOT SET!

GET /afcserver

Permissions:

NOT SET!

Roles:

NOT SET!

GET /afcserver/{id}

Permissions:

NOT SET!

Roles:

NOT SET!

GET /afcserver/statistics/{id}

Permissions:

NOT SET!

Roles:

NOT SET!

GET /afcserver/diagnostics/{id}

Permissions:

NOT SET!

Roles:

NOT SET!

GET /ap/afc/floorReport/{deviceId}

Permissions:

NOT SET!

Roles:

NOT SET!

GET /ap/afc/interface/details/{sn}

Permissions:

NOT SET!

Roles:

NOT SET!

POST /ap/spectrum

Permissions:

“ap-spectrum” – Permission to set AP spectrum

Roles:

"Operator",

"Administrator"

GET /aps/afc/query

Permissions:

NOT SET!

Roles:

NOT SET!

POST /aps/afc/query

Permissions:

NOT SET!

Roles:

NOT SET!

POST /aps/afc/update

Permissions:

NOT SET!

Roles:

NOT SET!

GET /floor/afc/details

Permissions:

"floor-afc-details" – Permission for full control of floor AFC details

"floor-afc-details:r" – Permission to read floor AFC details

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /floor/afc/details

Permissions:

"floor-afc-details" – Permission for full control of floor AFC details

Roles:

"Operator",

"Administrator"

POST /floor/afc/details

Permissions:

"floor-afc-details" – Permission for full control of floor AFC details

Roles:

"Operator",

"Administrator"

DELETE /floor/afc/details/{id}

Permissions:

"floor-afc-details" – Permission for full control of floor AFC details

Roles:

"Operator",

"Administrator"

GET /site/afc/schedule

Permissions:

"site-afc-schedule" – Permission for full control of site AFC schedule

"site-afc-schedule:r" – Permission to read site AFC schedule

Roles:

"Operator",

"Administrator",

"Monitor",

"Installer",

"Observer"

PUT /site/afc/schedule

Permissions:

"site-afc-schedule" – Permission for full control of site AFC schedule

Roles:

"Operator",
"Administrator"

POST /site/afc/schedule

Permissions:

"site-afc-schedule" – Permission for full control of site AFC schedule

Roles:

"Operator",
"Administrator"

POST /site/spectrum

Permissions:

NOT SET!

Roles:

NOT SET!

RTTS-endpoint

Permissions:

"rtts" – Permission for all API calls in the RTTS-endpoint Section

POST /rtts-endpoint

Permissions:

No Specific permission - included with "rtts"

Roles:

"Operator",
"Administrator"

POST /rtts-endpoint

Permissions:

No Specific permission - included with "rtts"

Roles:

"Operator",
"Administrator"

AIRRM-endpoint

No default permissions for this category

POST /airrm/ap/radioInfo

Permissions:

NOT SET!

Roles:

NOT SET!

POST /airrm/device/{sn}

Permissions:

NOT SET!

Roles:

NOT SET!

POST /airrm/radio/apInfo/:radioMac

Permissions:

NOT SET!

Roles:

NOT SET!

APPENDIX – A

API call list based on Roles

Administrator

All available API calls

Operator

All available API calls **except** for the following:

POST /users

DELETE /users/{id}

PATCH /users/{id}

POST /users/external

POST /users/data-usage

DELETE /users/external/{id}

PATCH /users/external/{id}

POST /filter-metadata

POST /users/grid

POST /users/grid-export

POST /users/type-distribution

Monitor

POST /logout

POST /auth/apitoken

GET /auth/apitoken/info

GET /auth/permissions

POST /auth/permissions/:check

GET /operations/{operationId}

POST /account/:switch

GET /account/external

GET /account/home

GET /account/third-party-applications

GET /account/vhm/setting

GET /account/vhm/status
GET /account/viq
GET /account/viq/default-device-password
GET /account/viq/download
GET /account/viq/export-import-status
GET /users
GET /users/{id}
POST /users/data-usage
POST /users/filter-metadata
POST /users/grid
POST /users/grid-export
GET /users/me
GET /users/reports/{id}
POST /users/type-distribution
GET /hiq/context
GET /hiq/context/creating
GET /hiq/context/reading
GET /hiq/organizations
GET /hiq/status
GET /locations/building
GET /locations/building/{id}
GET /locations/floor
GET /locations/floor/:floorId/label
GET /locations/floor/{id}
GET /locations/folder/:folderId/zones
GET /locations/site
GET /locations/site/{id}
GET /locations/tree
GET /locations/tree/devices
GET /locations/tree/maps
GET /locations/wall/type
GET /locations/wall/type/references/{id}
GET /devices
GET /devices/{id}
GET /devices/{id}/alarms
GET /devices/{id}/client-monitor
GET /devices/{id}/ftm-settings
GET /devices/{id}/gallery-image
GET /devices/{id}/geolocation
GET /devices/{id}/history/cpu-mem
GET /devices/{id}/ibeacon
GET /devices/{id}/installation-report
GET /devices/{id}/interfaces/wifi
GET /devices/{id}/iot
GET /devices/{id}/location

GET /devices/{id}/monitor/refresh/status
GET /devices/{id}/network-policy
GET /devices/{id}/radio-operating-mode
GET /devices/{id}/ssid/status
GET /devices/digital-twin
GET /devices/network-policy/{policyId}
GET /devices/radio-information
GET /devices/reports/{id}
POST /devices/rm-devices-connection-status
POST /devices/rm-devices-metadata
POST /devices/rm-devices-page
POST /devices/rm-devices-page/export
GET /devices/rm-devices-stack/{stackId}
GET /devices/stats
GET /network-policies
GET /network-policies/{id}
GET /network-policies/{id}/ssids
GET /clients/{id}
GET /clients/active
GET /clients/active/count
GET /clients/byMac/{clientMac}
GET /clients/summary
GET /clients/usage
POST /switch-inspector/diagnostics
POST /d360/client/graph
POST /d360/client/grid
POST /d360/wireless/surrounding-aps
POST /dashboard/alerts
POST /dashboard/assets
POST /dashboard/clients
POST /dashboard/devices
POST /dashboard/export
POST /dashboard/sites-with-issues
POST /dashboard/usage-capacity
POST /dashboard/wireless/dashboard/criteria
POST /dashboard/wired/usage-capacity/grid
POST /dashboard/wired/usage-capacity/usage-utilization
POST /dashboard/wired/usage-capacity/wired-congestion
POST /dashboard/wired/usage-capacity/wired-throughput
POST /dashboard/wired/client-health/grid
POST /dashboard/wired/client-health/ip-connectivity-issues
POST /dashboard/wired/client-health/port-congestion
POST /dashboard/wired/client-health/port-errors
POST /dashboard/wired/client-health/traffic-anomalies
POST /dashboard/wired/device-health/cpu-usage-issues

POST /dashboard/wired/device-health/fan-issues
POST /dashboard/wired/device-health/fan-status
POST /dashboard/wired/device-health/grid
POST /dashboard/wired/device-health/memory-usage-issues
POST /dashboard/wired/device-health/poe-usage-issues
POST /dashboard/wired/device-health/poe-usage-status
POST /dashboard/wired/device-health/psu-issues
POST /dashboard/wired/device-health/psu-status
POST /dashboard/wired/device-health/summary
POST /dashboard/wired/device-health/temperature-issues
POST /dashboard/wired/device-health/temperature-status
POST /dashboard/wireless/usage-capacity/excessive-packet-loss
POST /dashboard/wireless/usage-capacity/excessive-retries
POST /dashboard/wireless/usage-capacity/excessive-utilization
POST /dashboard/wireless/usage-capacity/export
POST /dashboard/wireless/usage-capacity/grid
POST /dashboard/wireless/client-health/connectivity-issues
POST /dashboard/wireless/client-health/export
POST /dashboard/wireless/client-health/filter-metadata
POST /dashboard/wireless/client-health/frequency-distribution
POST /dashboard/wireless/client-health/grid
POST /dashboard/wireless/client-health/issue/association
POST /dashboard/wireless/client-health/issue/authentication
POST /dashboard/wireless/client-health/issue/ipaddress
POST /dashboard/wireless/client-health/issue/roaming
POST /dashboard/wireless/client-health/roaming-issues
POST /dashboard/wireless/device-health/export
POST /dashboard/wireless/device-health/grid
POST /dashboard/wireless/device-health/issues/cpu-usage-issues
POST /dashboard/wireless/device-health/issues/memory-usage-issues
POST /dashboard/wireless/device-health/issues/poe-usage-issues
POST /dashboard/wireless/device-health/summary
GET /applications
GET /applications/{id}/clients/top{n}
GET /applications/reports/{id}
GET /applications/top{n}
POST /applications/usage/summary
POST /applications/usage/summary/export
GET /applications/usage/summary/meta-data
GET /alert-policies
GET /alert-policies/{id}
GET /alert-policies/{policyId}/rules/{ruleId}
GET /alert-policies/available-sites
GET /alert-subscriptions/emails
GET /alert-subscriptions/emails/{id}

GET /alert-subscriptions/servicenow
GET /alert-subscriptions/servicenow/{id}
GET /alert-subscriptions/webhooks
GET /alert-subscriptions/webhooks/{id}
GET /alerts
GET /alerts/count-by-{group}
GET /alerts/reports/{id}
GET /logs/accounting
GET /logs/audit
GET /logs/audit/full-descriptions/{id}
GET /logs/audit/reports/{id}
GET /logs/auth
GET /logs/credential
GET /logs/email
GET /logs/sms
GET /subscriptions/webhook
GET /subscriptions/webhook/export
GET /acct-api-token
GET /acct-api-token/export
GET /credential-distribution-groups
GET /third-party-api-connection
GET /deployments
GET /deployments/{deploymentId}
GET /deployments/{deploymentId}/status
GET /deployments/overview
GET /deployments/status
GET /vlan-profiles
GET /vlan-profiles/{id}
GET /email-templates
GET /endusers
GET /pcgs/key-based
GET /pcgs/key-based/network-policy-{policyId}/port-assignments
GET /pcgs/key-based/network-policy-{policyId}/users
GET /sms-templates
GET /usergroups
GET /usergroups:unique
GET /ccgs
GET /ccgs/{id}
GET /classification-rules
GET /classification-rules/{id}
GET /client-monitor-profiles
GET /client-monitor-profiles/{id}
GET /hotspot-profiles
GET /hotspot-profiles/{id}
GET /hotspot-service-provider-profiles

GET /hotspot-service-provider-profiles/{id}
GET /iot-profiles
GET /iot-profiles/{id}
GET /ip-firewall-policies
GET /ip-firewall-policies/{id}
GET /l3-address-profiles
GET /l3-address-profiles/{id}
GET /mac-firewall-policies
GET /mac-firewall-policies/{id}
GET /mac-object-profiles
GET /mac-object-profiles/{id}
GET /radio-profiles
GET /radio-profiles/{id}
GET /radio-profiles/channel-selection/{id}
GET /radio-profiles/mac-ouis
GET /radio-profiles/mac-ouis/{id}
GET /radio-profiles/miscellaneous/{id}
GET /radio-profiles/neighborhood-analysis/{id}
GET /radio-profiles/radio-usage-opt/{id}
GET /radio-profiles/sensor-scan/{id}
GET /radio-profiles/wmm-qos/{id}
GET /ssids
GET /ssids/advanced-settings/{id}
GET /user-profile-assignments
GET /user-profile-assignments/{id}
GET /user-profiles
GET /user-profiles/{id}
GET /network-services
GET /tunnel-concentrators
GET /tunnel-concentrators/{id}
GET /ad-servers
GET /cwps
GET /ldap-servers
GET /ldap-servers/{id}
GET /radius-client-objects
GET /radius-client-objects/{id}
GET /radius-proxies
GET /radius-proxies/{id}
GET /radius-proxies/devices
GET /radius-servers/external
GET /radius-servers/external/{id}
GET /radius-servers/internal
GET /radius-servers/internal/{id}
GET /radius-servers/internal/devices
GET /radsec-proxies

GET /radsec-proxies/{id}
GET /certificate-bundles
GET /certificate-bundles/{id}
GET /certificates
GET /copilot/connectivity/wired/events
GET /copilot/connectivity/wired/experience
GET /copilot/connectivity/wired/hardware
GET /copilot/connectivity/wired/locations/hardware
GET /copilot/connectivity/wired/quality-index
GET /copilot/connectivity/wireless/apps
GET /copilot/connectivity/wireless/events
GET /copilot/connectivity/wireless/experience
GET /copilot/connectivity/wireless/locations/events
GET /copilot/connectivity/wireless/locations/performance
GET /copilot/connectivity/wireless/locations/quality-index
GET /copilot/connectivity/wireless/locations/time-to-connect
GET /copilot/connectivity/wireless/performance
GET /copilot/connectivity/wireless/quality-index
GET /copilot/connectivity/wireless/time-to-connect
GET /copilot/connectivity/wireless/views
GET /copilot/anomalies/adverse-traffic/device-stats
GET /copilot/anomalies/adverse-traffic/packet-counts
GET /copilot/anomalies/anomalies-by-category
GET /copilot/anomalies/devices-by-location
GET /copilot/anomalies/devices-with-locations
GET /copilot/anomalies/dfs-recurrence/channel-stats
GET /copilot/anomalies/dfs-recurrence/count-stats
GET /copilot/anomalies/excluded-vlans-list
GET /copilot/anomalies/hardware-health/client-list
GET /copilot/anomalies/hardware-health/cpu-mem-stats
GET /copilot/anomalies/hardware-health/stats
GET /copilot/anomalies/locations
GET /copilot/anomalies/missing-vlan/count
GET /copilot/anomalies/notifications
GET /copilot/anomalies/poeflapping/lldp-cdp-info
GET /copilot/anomalies/poeflapping/stats
GET /copilot/anomalies/poeflapping/trends
GET /copilot/anomalies/port-efficiency/speed-duplex-stats
GET /copilot/anomalies/port-efficiency/stats
GET /copilot/anomalies/report
GET /copilot/anomalies/wifi-capacity/client-list
GET /copilot/anomalies/wifi-capacity/stats
GET /copilot/anomalies/wifi-efficiency/client-list
GET /copilot/anomalies/wifi-efficiency/stats
GET /copilot/assurance-scans/overview

GET /packetcaptures
GET /packetcaptures/{id}
GET /packetcaptures/files
GET /network-scorecard/clientHealth/{locationId}
GET /network-scorecard/deviceHealth/{locationId}
GET /network-scorecard/networkHealth/{locationId}
GET /network-scorecard/servicesHealth/{locationId}
GET /network-scorecard/wifiHealth/{locationId}
GET /countries
GET /countries/{countryAlpha2Code}/states
GET /countries/{countryCode}/:validate
GET /ng-reports/download/reports/:id
POST /ng-reports/downloads/reports
GET /ng-reports/information/
GET /ng-reports/information/:metrics
POST /ng-reports/metadata/application
POST /ng-reports/metadata/bands
POST /ng-reports/metadata/client
POST /ng-reports/metadata/device
POST /ng-reports/metadata/os
POST /ng-reports/metadata/ssids
POST /ng-reports/metadata/user
POST /ng-reports/tabledata
POST /ng-reports/timeseries
GET /ng-reports/scheduled/:reportId/recipients
POST /ng-reports/scheduled/:reportId/recipients
GET /ng-reports/scheduled/custom
POST /ng-reports/scheduled/custom
GET /ng-reports/scheduled/custom/:reportId
GET /ng-reports/scheduled/custom/:reportScheduleId/runs
GET /ng-reports/scheduled/network-summary
GET /ng-reports/scheduled/pci-compliance
GET /ng-reports/scheduled/reports/download
GET /ng-reports/scheduled/runs/:reportRunId/recipients
POST /afc/export
POST /afc/filter-metadata
GET /floor/afc/details
GET /site/afc/schedule

Installer

POST /logout
POST /auth/apitoken
POST /auth/permissions/:check
GET /operations/{operationId}
POST /account/:switch

GET /account/external
GET /account/home
GET /account/third-party-applications
GET /account/vhm/setting
GET /account/vhm/status
GET /account/viq
GET /account/viq/default-device-password
GET /account/viq/download
GET /account/viq/export-import-status
POST /users/data-usage
POST /users/filter-metadata
POST /users/grid
POST /users/grid-export
GET /users/me
GET /users/reports/{id}
POST /users/type-distribution
GET /hiq/context
PUT /hiq/context
GET /hiq/context/creating
PUT /hiq/context/creating
GET /hiq/context/reading
PUT /hiq/context/reading
GET /hiq/organizations
GET /hiq/status
POST /locations
POST /locations/:init
PUT /locations/{id}
DELETE /locations/{id}
GET /locations/building
POST /locations/building
GET /locations/building/{id}
PUT /locations/building/{id}
DELETE /locations/building/{id}
GET /locations/floor
POST /locations/floor
GET /locations/floor/{floorId}/label
PUT /locations/floor/{floorId}/label
POST /locations/floor/{floorId}/label
DELETE /locations/floor/{floorId}/label/{labelId}
GET /locations/floor/{id}
PUT /locations/floor/{id}
DELETE /locations/floor/{id}
PUT /locations/floor/bulk/label
POST /locations/floorplan
GET /locations/folder/{folderId}/zones

DELETE /locations/folder/zone/{id}
PUT /locations/folder/zones
POST /locations/folder/zones
POST /locations/import/ekahau
GET /locations/site
POST /locations/site
GET /locations/site/{id}
PUT /locations/site/{id}
DELETE /locations/site/{id}
GET /locations/tree
GET /locations/tree/devices
GET /locations/tree/maps
GET /locations/wall/type
POST /locations/wall/type
PUT /locations/wall/type/{id}
DELETE /locations/wall/type/{id}
GET /locations/wall/type/references/{id}
GET /devices
POST /devices/:advanced-onboard
POST /devices/:check-ownership
POST /devices/:cli
POST /devices/:delete
POST /devices/:manage
POST /devices/:onboard
POST /devices/:reboot
POST /devices/:reset
POST /devices/:ssh-active-sessions
POST /devices/:unmanage
GET /devices/{id}
DELETE /devices/{id}
POST /devices/{id}/:cli
POST /devices/{id}/:manage
POST /devices/{id}/:reboot
POST /devices/{id}/:reset
POST /devices/{id}/:unmanage
GET /devices/{id}/alarms
POST /devices/{id}/bounce-port
GET /devices/{id}/client-monitor
PUT /devices/{id}/client-monitor
DELETE /devices/{id}/client-monitor
PUT /devices/{id}/description
GET /devices/{id}/ftm-settings
PUT /devices/{id}/ftm-settings
DELETE /devices/{id}/ftm-settings
GET /devices/{id}/gallery-image

GET /devices/{id}/geolocation
GET /devices/{id}/history/cpu-mem
PUT /devices/{id}/hostname
GET /devices/{id}/ibeacon
GET /devices/{id}/installation-report
GET /devices/{id}/interfaces/wifi
GET /devices/{id}/iot
POST /devices/{id}/iot/:disable
POST /devices/{id}/iot/:enable
GET /devices/{id}/location
PUT /devices/{id}/location
DELETE /devices/{id}/location
PUT /devices/{id}/mobileapp/gps
POST /devices/{id}/monitor/:refresh
GET /devices/{id}/monitor/refresh/status
GET /devices/{id}/network-policy
PUT /devices/{id}/network-policy
DELETE /devices/{id}/network-policy
GET /devices/{id}/radio-operating-mode
PUT /devices/{id}/radio-operating-mode
POST /devices/{id}/ssid/:override
GET /devices/{id}/ssid/status
POST /devices/{id}/ssid/status/:change
POST /devices/{id}/thread/commissioner/:start
POST /devices/{id}/thread/commissioner/:stop
PUT /devices/{id}/visible
POST /devices/actions-support-metadata
POST /devices/anchor/assign
POST /devices/anchor/revoke
POST /devices/client-monitor/:assign
POST /devices/client-monitor/:revoke
POST /devices/client-monitor/:query
POST /devices/country-code/:assign
GET /devices/digital-twin
PUT /devices/ibeacon
POST /devices/location/:assign
POST /devices/location/:query
POST /devices/location/:revoke
POST /devices/network-policy/:assign
POST /devices/network-policy/:query
POST /devices/network-policy/:revoke
GET /devices/network-policy/{policyId}
POST /devices/os/:change
GET /devices/radio-information
PUT /devices/radius-proxy/:assign

DELETE /devices/radius-proxy/:revoke
GET /devices/reports/{id}
POST /devices/rm-devices-connection-status
POST /devices/rm-devices-metadata
POST /devices/rm-devices-page
POST /devices/rm-devices-page/export
GET /devices/rm-devices-stack/{stackId}
GET /devices/stats
POST /devices/thread/commissioner/start
POST /devices/thread/commissioner/stop
GET /network-policies
GET /network-policies/{id}
GET /network-policies/{id}/ssids
GET /clients/{id}
GET /clients/active
GET /clients/active/count
GET /clients/byMac/{clientMac}
GET /clients/summary
GET /clients/usage
POST /switch-inspector/diagnostics
POST /d360/client/graph
POST /d360/client/grid
POST /d360/wireless/surrounding-aps
POST /dashboard/alerts
POST /dashboard/assets
POST /dashboard/clients
POST /dashboard/devices
POST /dashboard/export
POST /dashboard/sites-with-issues
POST /dashboard/usage-capacity
POST /dashboard/wireless/dashboard/criteria
POST /dashboard/wired/usage-capacity/grid
POST /dashboard/wired/usage-capacity/usage-utilization
POST /dashboard/wired/usage-capacity/wired-congestion
POST /dashboard/wired/usage-capacity/wired-throughput
POST /dashboard/wired/client-health/grid
POST /dashboard/wired/client-health/ip-connectivity-issues
POST /dashboard/wired/client-health/port-congestion
POST /dashboard/wired/client-health/port-errors
POST /dashboard/wired/client-health/traffic-anomalies
POST /dashboard/wired/device-health/cpu-usage-issues
POST /dashboard/wired/device-health/fan-issues
POST /dashboard/wired/device-health/fan-status
POST /dashboard/wired/device-health/grid
POST /dashboard/wired/device-health/memory-usage-issues

POST /dashboard/wired/device-health/poe-usage-issues
POST /dashboard/wired/device-health/poe-usage-status
POST /dashboard/wired/device-health/psu-issues
POST /dashboard/wired/device-health/psu-status
POST /dashboard/wired/device-health/summary
POST /dashboard/wired/device-health/temperature-issues
POST /dashboard/wired/device-health/temperature-status
POST /dashboard/wireless/usage-capacity/excessive-packet-loss
POST /dashboard/wireless/usage-capacity/excessive-retries
POST /dashboard/wireless/usage-capacity/excessive-utilization
POST /dashboard/wireless/usage-capacity/export
POST /dashboard/wireless/usage-capacity/grid
POST /dashboard/wireless/client-health/connectivity-issues
POST /dashboard/wireless/client-health/export
POST /dashboard/wireless/client-health/filter-metadata
POST /dashboard/wireless/client-health/frequency-distribution
POST /dashboard/wireless/client-health/grid
POST /dashboard/wireless/client-health/issue/association
POST /dashboard/wireless/client-health/issue/authentication
POST /dashboard/wireless/client-health/issue/ipaddress
POST /dashboard/wireless/client-health/issue/roaming
POST /dashboard/wireless/client-health/roaming-issues
POST /dashboard/wireless/device-health/export
POST /dashboard/wireless/device-health/grid
POST /dashboard/wireless/device-health/issues/cpu-usage-issues
POST /dashboard/wireless/device-health/issues/memory-usage-issues
POST /dashboard/wireless/device-health/issues/poe-usage-issues
POST /dashboard/wireless/device-health/summary
GET /applications/reports/{id}
POST /applications/usage/summary
POST /applications/usage/summary/export
GET /applications/usage/summary/meta-data
GET /alert-policies
GET /alert-policies/{id}
GET /alert-policies/{policyId}/rules/{ruleId}
GET /alert-policies/available-sites
GET /alert-subscriptions/emails
GET /alert-subscriptions/emails/{id}
GET /alert-subscriptions/servicenow
GET /alert-subscriptions/servicenow/{id}
GET /alert-subscriptions/webhooks
GET /alert-subscriptions/webhooks/{id}
GET /alerts
GET /alerts/count-by-{group}
GET /alerts/reports/{id}

GET /logs/accounting
GET /logs/audit
GET /logs/audit/full-descriptions/{id}
GET /logs/audit/reports/{id}
GET /logs/auth
GET /logs/credential
GET /logs/email
GET /logs/sms
GET /acct-api-token
GET /acct-api-token/export
GET /deployments
GET /deployments/{deploymentId}
GET /deployments/{deploymentId}/status
GET /deployments/overview
GET /deployments/status
GET /client-monitor-profiles
GET /client-monitor-profiles/{id}
GET /hotspot-profiles
GET /hotspot-profiles/{id}
GET /hotspot-service-provider-profiles
GET /hotspot-service-provider-profiles/{id}
GET /iot-profiles
GET /iot-profiles/{id}
GET /ip-firewall-policies
GET /ip-firewall-policies/{id}
GET /mac-firewall-policies
GET /mac-firewall-policies/{id}
GET /mac-object-profiles
GET /mac-object-profiles/{id}
GET /radio-profiles
GET /radio-profiles/{id}
GET /radio-profiles/channel-selection/{id}
GET /radio-profiles/mac-ouis
GET /radio-profiles/mac-ouis/{id}
GET /radio-profiles/miscellaneous/{id}
GET /radio-profiles/neighborhood-analysis/{id}
GET /radio-profiles/radio-usage-opt/{id}
GET /radio-profiles/sensor-scan/{id}
GET /radio-profiles/wmm-qos/{id}
GET /ssids
GET /ssids/advanced-settings/{id}
GET /user-profile-assignments
GET /user-profile-assignments/{id}
GET /user-profiles
GET /user-profiles/{id}

GET /network-services
GET /tunnel-concentrators
GET /tunnel-concentrators/{id}
GET /radius-client-objects
GET /radius-client-objects/{id}
GET /radius-servers/external
GET /radius-servers/external/{id}
GET /radius-servers/internal
GET /radius-servers/internal/{id}
GET /radius-servers/internal/devices
GET /radsec-proxies
GET /radsec-proxies/{id}
GET /certificate-bundles
GET /certificate-bundles/{id}
GET /certificates
GET /packetcaptures
GET /packetcaptures/{id}
GET /packetcaptures/files
GET /network-scorecard/clientHealth/{locationId}
GET /network-scorecard/deviceHealth/{locationId}
GET /network-scorecard/networkHealth/{locationId}
GET /network-scorecard/servicesHealth/{locationId}
GET /network-scorecard/wifiHealth/{locationId}
GET /countries
GET /countries/{countryAlpha2Code}/states
GET /countries/{countryCode}/:validate
GET /ng-reports/download/reports/{id}
POST /ng-reports/downloads/reports
GET /ng-reports/information/
GET /ng-reports/information/{metrics}
POST /ng-reports/metadata/application
POST /ng-reports/metadata/bands
POST /ng-reports/metadata/client
POST /ng-reports/metadata/device
POST /ng-reports/metadata/os
POST /ng-reports/metadata/ssids
POST /ng-reports/metadata/user
POST /ng-reports/tabledata
POST /ng-reports/timeseries
GET /ng-reports/scheduled/{reportId}/recipients
POST /ng-reports/scheduled/{reportId}/recipients
GET /ng-reports/scheduled/custom
POST /ng-reports/scheduled/custom
GET /ng-reports/scheduled/custom/{reportId}
GET /ng-reports/scheduled/custom/{reportScheduleId}/runs

GET /ng-reports/scheduled/network-summary
GET /ng-reports/scheduled/pci-compliance
GET /ng-reports/scheduled/reports/download
GET /ng-reports/scheduled/runs/{reportRunId}/recipients
POST /afc/export
POST /afc/filter-metadata
POST /afc/mobileapp/apcandidates
GET /floor/afc/details
GET /site/afc/schedule

Observer

POST /logout
GET /auth/apitoken/info
GET /auth/permissions
POST /auth/permissions/:check
GET /operations/{operationId}
POST /account/:switch
GET /account/external
GET /account/home
GET /account/third-party-applications
GET /account/vhm/setting
GET /account/vhm/status
GET /account/viq
GET /account/viq/default-device-password
GET /account/viq/download
GET /account/viq/export-import-status
POST /users/data-usage
POST /users/filter-metadata
POST /users/grid
POST /users/grid-export
GET /users/me
GET /users/reports/{id}
POST /users/type-distribution
GET /hiq/context
GET /hiq/context/creating
GET /hiq/context/reading
GET /hiq/organizations
GET /hiq/status
GET /locations/building
GET /locations/building/{id}
GET /locations/floor
GET /locations/floor/{floorId}/label
GET /locations/floor/{id}
GET /locations/folder/{folderId}/zones
GET /locations/site

GET /locations/site/{id}
GET /locations/tree
GET /locations/tree/devices
GET /locations/tree/maps
GET /locations/wall/type
GET /locations/wall/type/references/{id}
GET /devices
GET /devices/{id}
GET /devices/{id}/alarms
GET /devices/{id}/client-monitor
GET /devices/{id}/ftm-settings
GET /devices/{id}/gallery-image
GET /devices/{id}/geolocation
GET /devices/{id}/history/cpu-mem
GET /devices/{id}/ibeacon
GET /devices/{id}/installation-report
GET /devices/{id}/interfaces/wifi
GET /devices/{id}/iot
GET /devices/{id}/location
GET /devices/{id}/monitor/refresh/status
GET /devices/{id}/network-policy
GET /devices/{id}/radio-operating-mode
GET /devices/{id}/ssid/status
GET /devices/digital-twin
GET /devices/network-policy/{policyId}
GET /devices/radio-information
GET /devices/reports/{id}
POST /devices/rm-devices-connection-status
POST /devices/rm-devices-metadata
POST /devices/rm-devices-page
POST /devices/rm-devices-page/export
GET /devices/rm-devices-stack/{stackId}
GET /devices/stats
GET /network-policies
GET /network-policies/{id}
GET /network-policies/{id}/ssids
GET /clients/{id}
GET /clients/active
GET /clients/active/count
GET /clients/byMac/{clientMac}
GET /clients/summary
GET /clients/usage
POST /switch-inspector/diagnostics
POST /d360/client/graph
POST /d360/client/grid

POST /d360/wireless/surrounding-aps
POST /dashboard/alerts
POST /dashboard/assets
POST /dashboard/clients
POST /dashboard/devices
POST /dashboard/export
POST /dashboard/sites-with-issues
POST /dashboard/usage-capacity
POST /dashboard/wireless/dashboard/criteria
POST /dashboard/wired/usage-capacity/grid
POST /dashboard/wired/usage-capacity/usage-utilization
POST /dashboard/wired/usage-capacity/wired-congestion
POST /dashboard/wired/usage-capacity/wired-throughput
POST /dashboard/wired/client-health/grid
POST /dashboard/wired/client-health/ip-connectivity-issues
POST /dashboard/wired/client-health/port-congestion
POST /dashboard/wired/client-health/port-errors
POST /dashboard/wired/client-health/traffic-anomalies
POST /dashboard/wired/device-health/cpu-usage-issues
POST /dashboard/wired/device-health/fan-issues
POST /dashboard/wired/device-health/fan-status
POST /dashboard/wired/device-health/grid
POST /dashboard/wired/device-health/memory-usage-issues
POST /dashboard/wired/device-health/poe-usage-issues
POST /dashboard/wired/device-health/poe-usage-status
POST /dashboard/wired/device-health/psu-issues
POST /dashboard/wired/device-health/psu-status
POST /dashboard/wired/device-health/summary
POST /dashboard/wired/device-health/temperature-issues
POST /dashboard/wired/device-health/temperature-status
POST /dashboard/wireless/usage-capacity/excessive-packet-loss
POST /dashboard/wireless/usage-capacity/excessive-retries
POST /dashboard/wireless/usage-capacity/excessive-utilization
POST /dashboard/wireless/usage-capacity/export
POST /dashboard/wireless/usage-capacity/grid
POST /dashboard/wireless/client-health/connectivity-issues
POST /dashboard/wireless/client-health/export
POST /dashboard/wireless/client-health/filter-metadata
POST /dashboard/wireless/client-health/frequency-distribution
POST /dashboard/wireless/client-health/grid
POST /dashboard/wireless/client-health/issue/association
POST /dashboard/wireless/client-health/issue/authentication
POST /dashboard/wireless/client-health/issue/ipaddress
POST /dashboard/wireless/client-health/issue/roaming
POST /dashboard/wireless/client-health/roaming-issues

POST /dashboard/wireless/device-health/export
POST /dashboard/wireless/device-health/grid
POST /dashboard/wireless/device-health/issues/cpu-usage-issues
POST /dashboard/wireless/device-health/issues/memory-usage-issues
POST /dashboard/wireless/device-health/issues/poe-usage-issues
POST /dashboard/wireless/device-health/summary
GET /applications
GET /applications/{id}/clients/top{n}
GET /applications/reports/{id}
GET /applications/top{n}
POST /applications/usage/summary
POST /applications/usage/summary/export
GET /applications/usage/summary/meta-data
GET /alert-policies
GET /alert-policies/{id}
GET /alert-policies/{policyId}/rules/{ruleId}
GET /alert-policies/available-sites
GET /alert-subscriptions/emails
GET /alert-subscriptions/emails/{id}
GET /alert-subscriptions/servicenow
GET /alert-subscriptions/servicenow/{id}
GET /alert-subscriptions/webhooks
GET /alert-subscriptions/webhooks/{id}
GET /alerts
GET /alerts/count-by-{group}
GET /alerts/reports/{id}
GET /logs/accounting
GET /logs/audit
GET /logs/audit/full-descriptions/{id}
GET /logs/audit/reports/{id}
GET /logs/auth
GET /logs/credential
GET /logs/email
GET /logs/sms
GET /subscriptions/webhook
GET /subscriptions/webhook/export
GET /acct-api-token
GET /acct-api-token/export
GET /credential-distribution-groups
GET /third-party-api-connection
GET /deployments
GET /deployments/{deploymentId}
GET /deployments/{deploymentId}/status
GET /deployments/overview
GET /deployments/status

GET /vlan-profiles
GET /vlan-profiles/{id}
GET /email-templates
GET /endusers
GET /pcgs/key-based
GET /pcgs/key-based/network-policy-{policyId}/port-assignments
GET /pcgs/key-based/network-policy-{policyId}/users
GET /sms-templates
GET /usergroups
GET /usergroups/:unique
GET /ccgs
GET /ccgs/{id}
GET /classification-rules
GET /classification-rules/{id}
GET /client-monitor-profiles
GET /client-monitor-profiles/{id}
GET /hotspot-profiles
GET /hotspot-profiles/{id}
GET /hotspot-service-provider-profiles
GET /hotspot-service-provider-profiles/{id}
GET /iot-profiles
GET /iot-profiles/{id}
GET /ip-firewall-policies
GET /ip-firewall-policies/{id}
GET /l3-address-profiles
GET /l3-address-profiles/{id}
GET /mac-firewall-policies
GET /mac-firewall-policies/{id}
GET /mac-object-profiles
GET /mac-object-profiles/{id}
GET /radio-profiles
GET /radio-profiles/{id}
GET /radio-profiles/channel-selection/{id}
GET /radio-profiles/mac-ouis
GET /radio-profiles/mac-ouis/{id}
GET /radio-profiles/miscellaneous/{id}
GET /radio-profiles/neighborhood-analysis/{id}
GET /radio-profiles/radio-usage-opt/{id}
GET /radio-profiles/sensor-scan/{id}
GET /radio-profiles/wmm-qos/{id}
GET /ssids
GET /ssids/advanced-settings/{id}
GET /user-profile-assignments
GET /user-profile-assignments/{id}
GET /user-profiles

GET /user-profiles/{id}
GET /network-services
GET /tunnel-concentrators
GET /tunnel-concentrators/{id}
GET /ad-servers
GET /cwps
GET /ldap-servers
GET /ldap-servers/{id}
GET /radius-client-objects
GET /radius-client-objects/{id}
GET /radius-proxies
GET /radius-proxies/{id}
GET /radius-proxies/devices
GET /radius-servers/external
GET /radius-servers/external/{id}
GET /radius-servers/internal
GET /radius-servers/internal/{id}
GET /radius-servers/internal/devices
GET /radsec-proxies
GET /radsec-proxies/{id}
GET /certificate-bundles
GET /certificate-bundles/{id}
GET /certificates
GET /copilot/connectivity/wired/events
GET /copilot/connectivity/wired/experience
GET /copilot/connectivity/wired/hardware
GET /copilot/connectivity/wired/locations/hardware
GET /copilot/connectivity/wired/quality-index
GET /copilot/connectivity/wireless/apps
GET /copilot/connectivity/wireless/events
GET /copilot/connectivity/wireless/experience
GET /copilot/connectivity/wireless/locations/events
GET /copilot/connectivity/wireless/locations/performance
GET /copilot/connectivity/wireless/locations/quality-index
GET /copilot/connectivity/wireless/locations/time-to-connect
GET /copilot/connectivity/wireless/performance
GET /copilot/connectivity/wireless/quality-index
GET /copilot/connectivity/wireless/time-to-connect
GET /copilot/connectivity/wireless/views
GET /copilot/anomalies/adverse-traffic/device-stats
GET /copilot/anomalies/adverse-traffic/packet-counts
GET /copilot/anomalies/anomalies-by-category
GET /copilot/anomalies/devices-by-location
GET /copilot/anomalies/devices-with-locations
GET /copilot/anomalies/dfs-recurrence/channel-stats

GET /copilot/anomalies/dfs-recurrence/count-stats
GET /copilot/anomalies/excluded-vlans-list
GET /copilot/anomalies/hardware-health/client-list
GET /copilot/anomalies/hardware-health/cpu-mem-stats
GET /copilot/anomalies/hardware-health/stats
GET /copilot/anomalies/locations
GET /copilot/anomalies/missing-vlan/count
GET /copilot/anomalies/notifications
GET /copilot/anomalies/poe-flapping/ldp-cdp-info
GET /copilot/anomalies/poe-flapping/stats
GET /copilot/anomalies/poe-flapping/trends
GET /copilot/anomalies/port-efficiency/speed-duplex-stats
GET /copilot/anomalies/port-efficiency/stats
GET /copilot/anomalies/report
GET /copilot/anomalies/wifi-capacity/client-list
GET /copilot/anomalies/wifi-capacity/stats
GET /copilot/anomalies/wifi-efficiency/client-list
GET /copilot/anomalies/wifi-efficiency/stats
GET /copilot/assurance-scans/overview
GET /packetcaptures
GET /packetcaptures/{id}
GET /packetcaptures/files
GET /network-scorecard/clientHealth/{locationId}
GET /network-scorecard/deviceHealth/{locationId}
GET /network-scorecard/networkHealth/{locationId}
GET /network-scorecard/servicesHealth/{locationId}
GET /network-scorecard/wifiHealth/{locationId}
GET /countries
GET /countries/{countryAlpha2Code}/states
GET /countries/{countryCode}/:validate
GET /ng-reports/scheduled/{reportId}/recipients
GET /ng-reports/scheduled/custom
GET /ng-reports/scheduled/custom/{reportId}
GET /ng-reports/scheduled/custom/{reportScheduleId}/runs
GET /ng-reports/scheduled/network-summary
GET /ng-reports/scheduled/pci-compliance
GET /ng-reports/scheduled/reports/download
GET /ng-reports/scheduled/runs/{reportRunId}/recipients
POST /afc/export
POST /afc/filter-metadata
GET /floor/afc/details
GET /site/afc/schedule

Help Desk

POST /logout

POST /auth/permissions/:check
GET /operations/{operationId}
POST /account/:switch
GET /account/external
GET /account/home
GET /account/third-party-applications
GET /account/vhm/setting
GET /account/vhm/status
GET /account/viq
GET /account/viq/default-device-password
GET /account/viq/download
GET /account/viq/export-import-status
POST /users/data-usage
POST /users/filter-metadata
POST /users/grid
POST /users/grid-export
GET /users/me
GET /users/reports/{id}
POST /users/type-distribution
GET /hiq/context
GET /hiq/context/creating
GET /hiq/context/reading
GET /hiq/organizations
GET /hiq/status
GET /locations/building
GET /locations/building/{id}
GET /locations/floor
GET /locations/floor/{floorId}/label
GET /locations/floor/{id}
GET /locations/folder/{folderId}/zones
GET /locations/site
GET /locations/site/{id}
GET /locations/tree
GET /locations/tree/devices
GET /locations/tree/maps
GET /locations/wall/type
GET /locations/wall/type/references/{id}
GET /clients/{id}
GET /clients/active
GET /clients/active/count
GET /clients/byMac/{clientMac}
GET /clients/summary
GET /clients/usage
GET /applications/reports/{id}
POST /applications/usage/summary

POST /applications/usage/summary/export
GET /applications/usage/summary/meta-data
GET /alerts
GET /alerts/count-by-**{group}**
GET /alerts/reports/**{id}**
GET /deployments
GET /deployments/**{deploymentId}**
GET /deployments/**{deploymentId}**/status
GET /deployments/overview
GET /deployments/status
GET /endusers
GET /packetcaptures
POST /packetcaptures
DELETE /packetcaptures
GET /packetcaptures/**{id}**
DELETE /packetcaptures/**{id}**
POST /packetcaptures/**{id}**/:stop
POST /packetcaptures/**{id}**/:upload
GET /packetcaptures/files
GET /countries
GET /countries/**{countryAlpha2Code}**/states
GET /countries/**{countryCode}**/:validate

Application Operator

POST /account/:switch
GET /account/external
GET /account/home
GET /account/third-party-applications
GET /account/vhm/setting
GET /account/vhm/status
GET /account/viq
GET /account/viq/default-device-password
GET /account/viq/download
GET /account/viq/export-import-status
GET /logs/accounting
GET /logs/audit
GET /logs/audit/full-descriptions/**{id}**
GET /logs/audit/reports/**{id}**
GET /logs/auth
GET /logs/credential
GET /logs/email
GET /logs/sms

Guest Management

POST /logout

POST /auth/permissions/:check
GET /operations/{operationId}
POST /account/:switch
GET /account/external
GET /account/home
GET /account/third-party-applications
GET /account/vhm/setting
GET /account/vhm/status
GET /account/viq
GET /account/viq/default-device-password
GET /account/viq/download
GET /account/viq/export-import-status
POST /switch-inspector/diagnostics
GET /credential-distribution-groups
GET /third-party-api-connection
GET /deployments
GET /deployments/{deploymentId}
GET /deployments/{deploymentId}/status
GET /deployments/overview
GET /deployments/status
GET /endusers
POST /endusers
PUT /endusers/{id}
DELETE /endusers/{id}
POST /endusers/{id}/:regenerate-password
GET /usergroups
GET /usergroups/:unique
GET /copilot/connectivity/wired/events
GET /copilot/connectivity/wired/experience
GET /copilot/connectivity/wired/hardware
GET /copilot/connectivity/wired/locations/hardware
GET /copilot/connectivity/wired/quality-index
GET /copilot/connectivity/wireless/apps
GET /copilot/connectivity/wireless/events
GET /copilot/connectivity/wireless/experience
GET /copilot/connectivity/wireless/locations/events
GET /copilot/connectivity/wireless/locations/performance
GET /copilot/connectivity/wireless/locations/quality-index
GET /copilot/connectivity/wireless/locations/time-to-connect
GET /copilot/connectivity/wireless/performance
GET /copilot/connectivity/wireless/quality-index
GET /copilot/connectivity/wireless/time-to-connect
GET /copilot/connectivity/wireless/views
GET /copilot/anomalies/adverse-traffic/device-stats
GET /copilot/anomalies/adverse-traffic/packet-counts

GET /copilot/anomalies/anomalies-by-category
GET /copilot/anomalies/devices-by-location
GET /copilot/anomalies/devices-with-locations
GET /copilot/anomalies/dfs-recurrence/channel-stats
GET /copilot/anomalies/dfs-recurrence/count-stats
GET /copilot/anomalies/excluded-vlans-list
GET /copilot/anomalies/hardware-health/client-list
GET /copilot/anomalies/hardware-health/cpu-mem-stats
GET /copilot/anomalies/hardware-health/stats
GET /copilot/anomalies/locations
GET /copilot/anomalies/missing-vlan/count
GET /copilot/anomalies/notifications
GET /copilot/anomalies/poeflapping/lldp-cdp-info
GET /copilot/anomalies/poeflapping/stats
GET /copilot/anomalies/poeflapping/trends
GET /copilot/anomalies/port-efficiency/speed-duplex-stats
GET /copilot/anomalies/port-efficiency/stats
GET /copilot/anomalies/report
GET /copilot/anomalies/wifi-capacity/client-list
GET /copilot/anomalies/wifi-capacity/stats
GET /copilot/anomalies/wifi-efficiency/client-list
GET /copilot/anomalies/wifi-efficiency/stats
GET /copilot/assurance-scans/overview

APPENDIX – B

API call list based on Permission

logout

POST /logout

auth

POST /auth/permissions/:check

POST /auth/apitoken

POST /auth/apitoken/:validate

GET /auth/permissions

GET /auth/apitoken/info

auth:r

GET /auth/permissions

GET /auth/apitoken/info

token:new

POST /auth/apitoken

perm:check

POST /auth/permissions/:check

lro

POST /operations/{operationId}/:cancel

GET /operations/{operationId}

DELETE /operations/{operationId}

lro:r

GET /operations/{operationId}

account

GET /account/viq/default-device-password

PUT /account/viq/default-device-password

PUT /account/vhm/setting/{id}

POST /account/viq/import

POST /account/viq/export

POST /account/viq/:reset

POST /account/viq/:backup

POST /account/:switch

GET /account/viq

GET /account/viq/export-import-status

GET /account/viq/download

GET /account/vhm/status

GET /account/vhm/setting

GET /account/third-party-applications

GET /account/home

GET /account/external

account:switch

POST /account/:switch

account:r

GET /account/viq/default-device-password

GET /account/viq

GET /account/viq/export-import-status

GET /account/viq/download

GET /account/vhm/status

GET /account/vhm/setting

GET /account/third-party-applications

GET /account/home

GET /account/external

viq:backup

POST /account/viq/:backup

backup-history

POST /backup/history/:restore
DELETE /backup/history/delete

viq:default-device-password

PUT /v1/account/viq/default-device-password

hiq

GET /hiq/context
PUT /hiq/context
GET /hiq/context/reading
PUT /hiq/context/reading
GET /hiq/context/creating
PUT /hiq/context/creating
GET /hiq/organizations
POST /hiq/organizations
POST /hiq/organizations/{id}:/rename
GET /hiq/status
DELETE /hiq/organizations/{id}

hiq:r

GET /hiq/context
GET /hiq/context/reading
GET /hiq/context/creating
GET /hiq/organizations
GET /hiq/status

org

GET /hiq/organizations
POST /hiq/organizations
POST /hiq/organizations/{id}:/rename
DELETE /hiq/organizations/{id}

org:new

POST /hiq/organizations

org:del

DELETE /hiq/organizations/{id}

org:rename

POST /hiq/organizations/{id}:/rename

hiq.ctx

GET /hiq/context
PUT /hiq/context

GET /hiq/context/reading
PUT /hiq/context/reading
GET /hiq/context/creating
PUT /hiq/context/creating

hiq.ctx:r

GET /hiq/context
GET /hiq/context/reading
GET /hiq/context/creating

hiq.ctx:w

PUT /hiq/context
PUT /hiq/context/reading
PUT /hiq/context/creating

device

PUT /devices/{id}/visible
GET /devices/{id}/radio-operating-mode
PUT /devices/{id}/radio-operating-mode
GET /devices/{id}/network-policy
PUT /devices/{id}/network-policy
DELETE /devices/{id}/network-policy
PUT /devices/{id}/mobileapp/gps
GET /devices/{id}/location
PUT /devices/{id}/location
DELETE /devices/{id}/location
PUT /devices/{id}/hostname
GET /devices/{id}/ftm-settings
PUT /devices/{id}/ftm-settings
DELETE /devices/{id}/ftm-settings
PUT /devices/{id}/description
GET /devices/{id}/client-monitor
PUT /devices/{id}/client-monitor
DELETE /devices/{id}/client-monitor
PUT /devices/radius-proxy/:assign
PUT /devices/ibeacon
POST /devices/{id}/thread/commissioner/:stop
POST /devices/{id}/thread/commissioner/:start
POST /devices/{id}/ssid/status/:change
POST /devices/{id}/ssid/:override
POST /devices/{id}/monitor/:refresh
POST /devices/{id}/iot/:enable
POST /devices/{id}/iot/:disable
POST /devices/{id}/bounce-port
POST /devices/{id}/:unmanage

POST /devices/{id}/:reset
POST /devices/{id}/:reboot
POST /devices/{id}/:manage
POST /devices/{id}/:cli
POST /devices/thread/commissioner/stop
POST /devices/thread/commissioner/start
POST /devices/rm-devices-page
POST /devices/rm-devices-page/export
POST /devices/rm-devices-metadata
POST /devices/rm-devices-connection-status
POST /devices/os/:change
POST /devices/network-policy/:revoke
POST /devices/network-policy/:query
POST /devices/network-policy/:assign
POST /devices/location/:revoke
POST /devices/location/:query
POST /devices/location/:assign
POST /devices/country-code/:assign
POST /devices/client-monitor/:revoke
POST /devices/client-monitor/:query
POST /devices/client-monitor/:assign
POST /devices/anchor/revoke
POST /devices/anchor/assign
POST /devices/actions-support-metadata
POST /devices/:unmanage
POST /devices/:ssh-active-sessions
POST /devices/:reset
POST /devices/:reboot
POST /devices/:onboard
POST /devices/:manage
POST /devices/:delete
POST /devices/:cli
POST /devices/:check-ownership
POST /devices/:advanced-onboard
GET /devices
GET /devices/{id}
DELETE /devices/{id}
GET /devices/{id}/ssid/status
GET /devices/{id}/monitor/refresh/status
GET /devices/{id}/iot
GET /devices/{id}/interfaces/wifi
GET /devices/{id}/installation-report
GET /devices/{id}/ibeacon
GET /devices/{id}/history/cpu-mem
GET /devices/{id}/geolocation

GET /devices/{id}/gallery-image
GET /devices/{id}/alarms
GET /devices/stats
GET /devices/rm-devices-stack/{stackId}
GET /devices/reports/{id}
GET /devices/radio-information
GET /devices/network-policy/{policyId}
GET /devices/digital-twin
DELETE /devices/radius-proxy/:revoke

device:r

GET /devices/{id}/radio-operating-mode
GET /devices/{id}/network-policy
GET /devices/{id}/location
GET /devices/{id}/ftm-settings
GET /devices/{id}/client-monitor
GET /devices
GET /devices/{id}
GET /devices/{id}/ssid/status
GET /devices/{id}/monitor/refresh/status
GET /devices/{id}/iot
GET /devices/{id}/interfaces/wifi
GET /devices/{id}/installation-report
GET /devices/{id}/ibeacon
GET /devices/{id}/history/cpu-mem
GET /devices/{id}/geolocation
GET /devices/{id}/gallery-image
GET /devices/{id}/alarms
GET /devices/stats
GET /devices/rm-devices-stack/{stackId}
GET /devices/reports/{id}
GET /devices/radio-information
GET /devices/network-policy/{policyId}
GET /devices/digital-twin

device:list

GET /devices

device:view

GET /devices/{id}
GET /devices/stats
GET /devices/radio-information
GET /devices/digital-twin

device:relaxed_read

POST /devices/rm-devices-page
POST /devices/rm-devices-page/export
POST /devices/rm-devices-metadata
POST /devices/rm-devices-connection-status

device:new

POST /devices/:onboard

device:del

POST /devices/:delete

device:cli

POST /devices/:cli

device:deploy

Permission not used

device:manage

POST /devices/:manage

device:unmanage

POST /devices/:unmanage

device:reboot

POST /devices/:reboot

device:reset

POST /devices/{id}/:reset

device:thread-commissioner

POST /devices/{id}/thread/commissioner/:stop
POST /devices/{id}/thread/commissioner/:start

d360:relaxed_read

POST /d360/wireless/surrounding-aps
POST /d360/client/grid
POST /d360/client/graph

dashboard:relaxed_read

POST /dashboard/wireless/usage-capacity/grid
POST /dashboard/wireless/usage-capacity/export
POST /dashboard/wireless/usage-capacity/excessive-utilization
POST /dashboard/wireless/usage-capacity/excessive-retries
POST /dashboard/wireless/usage-capacity/excessive-packet-loss
POST /dashboard/wireless/device-health/summary

POST /dashboard/wireless/device-health/issues/poe-usage-issues
POST /dashboard/wireless/device-health/issues/memory-usage-issues
POST /dashboard/wireless/device-health/issues/cpu-usage-issues
POST /dashboard/wireless/device-health/grid
POST /dashboard/wireless/device-health/export
POST /dashboard/wireless/dashboard/criteria
POST /dashboard/wireless/client-health/roaming-issues
POST /dashboard/wireless/client-health/issue/roaming
POST /dashboard/wireless/client-health/issue/ipaddress
POST /dashboard/wireless/client-health/issue/authentication
POST /dashboard/wireless/client-health/issue/association
POST /dashboard/wireless/client-health/grid
POST /dashboard/wireless/client-health/frequency-distribution
POST /dashboard/wireless/client-health/filter-metadata
POST /dashboard/wireless/client-health/export
POST /dashboard/wireless/client-health/connectivity-issues
POST /dashboard/wired/usage-capacity/wired-throughput
POST /dashboard/wired/usage-capacity/wired-congestion
POST /dashboard/wired/usage-capacity/usage-utilization
POST /dashboard/wired/usage-capacity/grid
POST /dashboard/wired/device-health/temperature-status
POST /dashboard/wired/device-health/temperature-issues
POST /dashboard/wired/device-health/summary
POST /dashboard/wired/device-health/psu-status
POST /dashboard/wired/device-health/psu-issues
POST /dashboard/wired/device-health/poe-usage-status
POST /dashboard/wired/device-health/poe-usage-issues
POST /dashboard/wired/device-health/memory-usage-issues
POST /dashboard/wired/device-health/grid
POST /dashboard/wired/device-health/fan-status
POST /dashboard/wired/device-health/fan-issues
POST /dashboard/wired/device-health/cpu-usage-issues
POST /dashboard/wired/client-health/traffic-anomalies
POST /dashboard/wired/client-health/port-errors
POST /dashboard/wired/client-health/port-congestion
POST /dashboard/wired/client-health/ip-connectivity-issues
POST /dashboard/wired/client-health/grid
POST /dashboard/usage-capacity
POST /dashboard/sites-with-issues
POST /dashboard/export
POST /dashboard/devices
POST /dashboard/clients
POST /dashboard/assets
POST /dashboard/alerts

client

PUT /clients/alias
POST /clients/disconnect
GET /clients/{id}
GET /clients/usage
GET /clients/summary
GET /clients/byMac/{clientMac}
DELETE /clients/byMac/{clientMac}
GET /clients/active
GET /clients/active/count

client:r

GET /clients/{id}
GET /clients/usage
GET /clients/summary
GET /clients/byMac/{clientMac}
GET /clients/active
GET /clients/active/count

applications-reports

GET /applications/reports/{id}

applications-usage

POST /applications/usage/summary
POST /applications/usage/summary/export
GET /applications/usage/summary/meta-data

locations

PUT /locations/{id}
DELETE /locations/{id}
PUT /locations/wall/type/{id}
DELETE /locations/wall/type/{id}
GET /locations/site/{id}
PUT /locations/site/{id}
DELETE /locations/site/{id}
PUT /locations/folder/zones
POST /locations/folder/zones
GET /locations/floor/{id}
PUT /locations/floor/{id}
DELETE /locations/floor/{id}
GET /locations/floor/{floorId}/label
PUT /locations/floor/{floorId}/label
POST /locations/floor/{floorId}/label
PUT /locations/floor/bulk/label
GET /locations/building/{id}

PUT /locations/building/{id}
DELETE /locations/building/{id}
POST /locations
GET /locations/wall/type
POST /locations/wall/type
GET /locations/site
POST /locations/site
POST /locations/import/ekahau
POST /locations/floorplan
GET /locations/floor
POST /locations/floor
GET /locations/building
POST /locations/building
POST /locations/.init
GET /locations/wall/type/references/{id}
GET /locations/tree
GET /locations/tree/maps
GET /locations/tree/devices
GET /locations/folder/{folderId}/zones
DELETE /locations/folder/zone/{id}
DELETE /locations/floor/{floorId}/label/{labelId}

locations:r

GET /locations/site/{id}
GET /locations/floor/{id}
GET /locations/floor/{floorId}/label
GET /locations/building/{id}
GET /locations/wall/type
GET /locations/site
GET /locations/floor
GET /locations/building
GET /locations/wall/type/references/{id}
GET /locations/tree
GET /locations/tree/maps
GET /locations/tree/devices
GET /locations/folder/{folderId}/zones

locations:floor-map-labels

GET /locations/floor/{floorId}/label
PUT /locations/floor/{floorId}/label
POST /locations/floor/{floorId}/label
PUT /locations/floor/bulk/label
DELETE /locations/floor/{floorId}/label/{labelId}

network-policy

GET /network-policies/{id}
PUT /network-policies/{id}
DELETE /network-policies/{id}
GET /network-policies
POST /network-policies
POST /network-policies/{id}/ssids/remove
POST /network-policies/{id}/ssids/add
GET /network-policies/{id}/ssids

policy:ssid

POST /network-policies/{id}/ssids/remove
POST /network-policies/{id}/ssids/add

network-policy:r

GET /network-policies/{id}
GET /network-policies
GET /network-policies/{id}/ssids

network-scorecard

GET /network-scorecard/wifiHealth/{locationId}
GET /network-scorecard/servicesHealth/{locationId}
GET /network-scorecard/networkHealth/{locationId}
GET /network-scorecard/deviceHealth/{locationId}
GET /network-scorecard/clientHealth/{locationId}

network-scorecard:r

GET /network-scorecard/wifiHealth/{locationId}
GET /network-scorecard/servicesHealth/{locationId}
GET /network-scorecard/networkHealth/{locationId}
GET /network-scorecard/deviceHealth/{locationId}
GET /network-scorecard/clientHealth/{locationId}

ssid

PUT /ssids/{id}/psk/password
PUT /ssids/{id}/mode/wep
PUT /ssids/{id}/mode/psk
PUT /ssids/{id}/mode/ppsk
PUT /ssids/{id}/mode/open
PUT /ssids/{id}/mode/dot1x
GET /ssids/advanced-settings/{id}
PUT /ssids/advanced-settings/{id}
POST /ssids/{id}/user-profile/attach
POST /ssids/{id}/user-profile-assignment/attach
POST /ssids/{id}/radius-server-group/attach

POST /ssids/{id}/radius-client-profile/:attach
POST /ssids/{id}/cwp/:enable
POST /ssids/{id}/cwp/:disable
POST /ssids/{id}/cwp/:attach
POST /ssids/{id}/client-monitor-profile/:attach
POST /ssids/{id}/:rename
GET /ssids

ssid:r

GET /ssids/advanced-settings/{id}
GET /ssids

pcg:key

GET /pcgs/key-based/network-policy-{policyId}/users
PUT /pcgs/key-based/network-policy-{policyId}/users
POST /pcgs/key-based/network-policy-{policyId}/users
DELETE /pcgs/key-based/network-policy-{policyId}/users
GET /pcgs/key-based
POST /pcgs/key-based
GET /pcgs/key-based/network-policy-{policyId}/port-assignments
POST /pcgs/key-based/network-policy-{policyId}/port-assignments
POST /pcgs/key-based/network-policy-{policyId}/keys/:generate
POST /pcgs/key-based/network-policy-{policyId}/keys/:email
POST /pcgs/key-based/network-policy-{policyId}/:onboard
DELETE /pcgs/key-based/network-policy-{policyId}

pcg:key:r

GET /pcgs/key-based/network-policy-{policyId}/users
GET /pcgs/key-based
GET /pcgs/key-based/network-policy-{policyId}/port-assignments

subscriptions-webhook

PUT /subscriptions/webhook/{id}
GET /subscriptions/webhook
POST /subscriptions/webhook
GET /subscriptions/webhook/export
DELETE /subscriptions/webhook/:delete

subscriptions-webhook:r

GET /subscriptions/webhook
GET /subscriptions/webhook/export

ccg

GET /ccgs/{id}
PUT /ccgs/{id}

DELETE /ccgs/{id}
GET /ccgs
POST /ccgs

ccg:r

GET /ccgs/{id}
GET /ccgs

log

POST /logs/audit/reports
GET /logs/sms
GET /logs/email
GET /logs/credential
GET /logs/auth
GET /logs/audit
GET /logs/audit/reports/{id}
GET /logs/audit/full-descriptions/{id}
GET /logs/accounting

log:r

GET /logs/sms
GET /logs/email
GET /logs/credential
GET /logs/auth
GET /logs/audit
GET /logs/audit/reports/{id}
GET /logs/audit/full-descriptions/{id}
GET /logs/accounting

cwp

GET /cwps

cwp:r

GET /cwps

sms-tmpl

GET /sms-templates

sms-tmpl:r

GET /sms-templates

class-rule

GET /classification-rules/{id}
PUT /classification-rules/{id}
DELETE /classification-rules/{id}

GET /classification-rules
POST /classification-rules

class-rule:r

GET /classification-rules/{id}
GET /classification-rules

user-profile

GET /user-profiles/{id}
PUT /user-profiles/{id}
DELETE /user-profiles/{id}
GET /user-profiles
POST /user-profiles
POST /user-profiles/{id}/mac-firewall-policies/:detach
POST /user-profiles/{id}/mac-firewall-policies/:attach
POST /user-profiles/{id}/ip-firewall-policies/:detach
POST /user-profiles/{id}/ip-firewall-policies/:attach

user-profile:r

GET /user-profiles/{id}
GET /user-profiles

mac-object-profiles

GET /mac-object-profiles/{id}
PUT /mac-object-profiles/{id}
DELETE /mac-object-profiles/{id}
GET /mac-object-profiles
POST /mac-object-profiles

mac-object-profiles:r

GET /mac-object-profiles/{id}
GET /mac-object-profiles

mac-firewall-policies

GET /mac-firewall-policies/{id}
PUT /mac-firewall-policies/{id}
DELETE /mac-firewall-policies/{id}
GET /mac-firewall-policies
POST /mac-firewall-policies
POST /mac-firewall-policies/{id}/mac-firewall-rule/:detach
POST /mac-firewall-policies/{id}/mac-firewall-rule/:attach

mac-firewall-policies:r

GET /mac-firewall-policies/{id}
GET /mac-firewall-policies

ip-firewall-policies

GET /ip-firewall-policies/{id}
PUT /ip-firewall-policies/{id}
DELETE /ip-firewall-policies/{id}
GET /ip-firewall-policies
POST /ip-firewall-policies
POST /ip-firewall-policies/{id}/ip-firewall-rule/:detach
POST /ip-firewall-policies/{id}/ip-firewall-rule/:attach

ip-firewall-policies:r

GET /ip-firewall-policies/{id}
GET /ip-firewall-policies

tunnel-concentrator

GET /tunnel-concentrators/{id}
PUT /tunnel-concentrators/{id}
DELETE /tunnel-concentrators/{id}
GET /tunnel-concentrators
POST /tunnel-concentrators

tunnel-concentrator:r

GET /tunnel-concentrators/{id}
GET /tunnel-concentrators

network-services

GET /network-services
POST /network-services
DELETE /network-services/{id}

network-services:r

GET /network-services

radius-proxy

GET /radius-proxies/{id}
PUT /radius-proxies/{id}
DELETE /radius-proxies/{id}
GET /radius-proxies
POST /radius-proxies
GET /radius-proxies/devices

radius-proxy:r

GET /radius-proxies/{id}
GET /radius-proxies
GET /radius-proxies/devices

radius-server

GET /radius-servers/internal/{id}
PUT /radius-servers/internal/{id}
DELETE /radius-servers/internal/{id}
GET /radius-servers/external/{id}
PUT /radius-servers/external/{id}
DELETE /radius-servers/external/{id}
GET /radius-servers/internal
POST /radius-servers/internal
DELETE /radius-servers/internal
GET /radius-servers/external
POST /radius-servers/external
GET /radius-servers/internal/devices

radius-server:r

GET /radius-servers/internal/{id}
GET /radius-servers/external/{id}
GET /radius-servers/internal
GET /radius-servers/external
GET /radius-servers/internal/devices

radsec-proxies

GET /radsec-proxies/{id}
PUT /radsec-proxies/{id}
DELETE /radsec-proxies/{id}
GET /radsec-proxies
POST /radsec-proxies

radsec-proxies:r

GET /radsec-proxies/{id}
GET /radsec-proxies

usergroup

PUT /usergroups/{id}
DELETE /usergroups/{id}
GET /usergroups
POST /usergroups
GET /usergroups/:unique

usergroup:r

GET /usergroups
GET /usergroups/:unique

credential-distribution-groups

PUT /credential-distribution-groups/{id}

GET /credential-distribution-groups
POST /credential-distribution-groups
DELETE /credential-distribution-groups

credential-distribution-groups:r

GET /credential-distribution-groups

third-party-api-connection

GET /third-party-api-connection
PUT /third-party-api-connection
DELETE /third-party-api-connection

third-party-api-connection:r

GET /third-party-api-connection

deployment

GET /deployments/{deploymentId}
PUT /deployments/{deploymentId}
DELETE /deployments/{deploymentId}
GET /deployments
POST /deployments
POST /deployments/firmware-metadatas
GET /deployments/{deploymentId}/status
GET /deployments/status
GET /deployments/overview

deployment:r

GET /deployments/{deploymentId}
GET /deployments
GET /deployments/{deploymentId}/status
GET /deployments/status
GET /deployments/overview

ad-server

GET /ad-servers

ad-server:r

GET /ad-servers

alert

POST /alerts/reports
POST /alerts/:acknowledge
GET /alerts
GET /alerts/reports/{id}
GET /alerts/count-by-{group}

alert:r

GET /alerts
GET /alerts/reports/{id}
GET /alerts/count-by-{group}

alert-policies

GET /alert-policies/{policyId}/rules/{ruleId}
PUT /alert-policies/{policyId}/rules/{ruleId}
GET /alert-policies/{id}
PUT /alert-policies/{id}
DELETE /alert-policies/{id}
GET /alert-policies
POST /alert-policies
POST /alert-policies/{policyId}/rules/{ruleId}/:enable
POST /alert-policies/{policyId}/rules/{ruleId}/:disable
GET /alert-policies/available-sites

alert-policies:r

GET /alert-policies/{policyId}/rules/{ruleId}
GET /alert-policies/{id}
GET /alert-policies
GET /alert-policies/available-sites

alert-subscriptions

GET /alert-subscriptions/webhooks/{id}
PUT /alert-subscriptions/webhooks/{id}
DELETE /alert-subscriptions/webhooks/{id}
GET /alert-subscriptions/servicenow/{id}
PUT /alert-subscriptions/servicenow/{id}
PATCH /alert-subscriptions/servicenow/{id}
GET /alert-subscriptions/emails/{id}
PUT /alert-subscriptions/emails/{id}
DELETE /alert-subscriptions/emails/{id}
GET /alert-subscriptions/webhooks
POST /alert-subscriptions/webhooks
POST /alert-subscriptions/webhooks/:delete
GET /alert-subscriptions/servicenow
POST /alert-subscriptions/servicenow
POST /alert-subscriptions/servicenow/:delete
GET /alert-subscriptions/emails
POST /alert-subscriptions/emails
POST /alert-subscriptions/emails/{id}/:verify
POST /alert-subscriptions/emails/:delete

alert-subscriptions:r

GET /alert-subscriptions/webhooks/{id}
GET /alert-subscriptions/servicenow/{id}
GET /alert-subscriptions/emails/{id}
GET /alert-subscriptions/webhooks
GET /alert-subscriptions/servicenow
GET /alert-subscriptions/emails

app

POST /applications/usage/summary
POST /applications/usage/summary/export
GET /applications
GET /applications/{id}/clients/top{n}
GET /applications/usage/summary/meta-data
GET /applications/top{n}
GET /applications/reports/{id}

application:r

GET /applications
GET /applications/{id}/clients/top{n}
GET /applications/usage/summary/meta-data
GET /applications/top{n}
GET /applications/reports/{id}

l3-address-profile

GET /l3-address-profiles/{id}
PUT /l3-address-profiles/{id}
DELETE /l3-address-profiles/{id}
GET /l3-address-profiles
POST /l3-address-profiles

l3-address-profile:r

GET /l3-address-profiles/{id}
GET /l3-address-profiles

vlan-profile

GET /vlan-profiles
POST /vlan-profiles
POST /vlan-profiles/:delete
GET /vlan-profiles/{id}
DELETE /vlan-profiles/{id}
PATCH /vlan-profiles/{id}

vlan-profile:r

GET /vlan-profiles

GET /vlan-profiles/{id}

enduser

PUT /endusers/{id}

DELETE /endusers/{id}

GET /endusers

POST /endusers

POST /endusers/{id}/:regenerate-password

enduser:r

GET /endusers

radius-client-object

GET /radius-client-objects/{id}

PUT /radius-client-objects/{id}

DELETE /radius-client-objects/{id}

GET /radius-client-objects

POST /radius-client-objects

radius-client-object:r

GET /radius-client-objects/{id}

GET /radius-client-objects

ldap-server

GET /ldap-servers/{id}

PUT /ldap-servers/{id}

DELETE /ldap-servers/{id}

GET /ldap-servers

POST /ldap-servers

ldap-server:r

GET /ldap-servers/{id}

GET /ldap-servers

email-template

GET /email-templates

email-template:r

GET /email-templates

certificate

POST /certificates/import

GET /certificates

DELETE /certificates/{id}

certificate:r

GET /certificates

certificate-bundles

GET /certificate-bundles/{id}

PUT /certificate-bundles/{id}

DELETE /certificate-bundles/{id}

GET /certificate-bundles

POST /certificate-bundles

certificate-bundles:r

GET /certificate-bundles/{id}

GET /certificate-bundles

radio-profile

GET /radio-profiles/{id}

PUT /radio-profiles/{id}

DELETE /radio-profiles/{id}

GET /radio-profiles/wmm-qos/{id}

PUT /radio-profiles/wmm-qos/{id}

GET /radio-profiles/sensor-scan/{id}

PUT /radio-profiles/sensor-scan/{id}

GET /radio-profiles/radio-usage-opt/{id}

PUT /radio-profiles/radio-usage-opt/{id}

GET /radio-profiles/neighborhood-analysis/{id}

PUT /radio-profiles/neighborhood-analysis/{id}

GET /radio-profiles/miscellaneous/{id}

PUT /radio-profiles/miscellaneous/{id}

GET /radio-profiles/mac-ouis/{id}

PUT /radio-profiles/mac-ouis/{id}

DELETE /radio-profiles/mac-ouis/{id}

GET /radio-profiles/channel-selection/{id}

PUT /radio-profiles/channel-selection/{id}

GET /radio-profiles

POST /radio-profiles

GET /radio-profiles/mac-ouis

POST /radio-profiles/mac-ouis

radio-profile:r

GET /radio-profiles/{id}

GET /radio-profiles/wmm-qos/{id}

GET /radio-profiles/sensor-scan/{id}

GET /radio-profiles/radio-usage-opt/{id}

GET /radio-profiles/neighborhood-analysis/{id}

GET /radio-profiles/miscellaneous/{id}

GET /radio-profiles/mac-ouis/{id}
GET /radio-profiles/channel-selection/{id}
GET /radio-profiles
GET /radio-profiles/mac-ouis

iot-profile

GET /iot-profiles/{id}
PUT /iot-profiles/{id}
DELETE /iot-profiles/{id}
GET /iot-profiles
POST /iot-profiles

iot-profile:r

GET /iot-profiles/{id}
GET /iot-profiles

client-monitor-profile

GET /client-monitor-profiles/{id}
PUT /client-monitor-profiles/{id}
DELETE /client-monitor-profiles/{id}
GET /client-monitor-profiles
POST /client-monitor-profiles

client-monitor-profile:r

GET /client-monitor-profiles/{id}
GET /client-monitor-profiles

user-profile-assignments

GET /user-profile-assignments
POST /user-profile-assignments
GET /user-profile-assignments/{id}
DELETE /user-profile-assignments/{id}

user-profile-assignments:r

GET /user-profile-assignments
GET /user-profile-assignments/{id}

switch-inspector

POST /switch-inspector/diagnostics

copilot-connectivity-wired:r

GET /copilot/connectivity/wired/quality-index
GET /copilot/connectivity/wired/locations/hardware
GET /copilot/connectivity/wired/hardware
GET /copilot/connectivity/wired/experience

GET /copilot/connectivity/wired/events

copilot-connectivity-wireless:r

GET /copilot/connectivity/wireless/views

GET /copilot/connectivity/wireless/time-to-connect

GET /copilot/connectivity/wireless/quality-index

GET /copilot/connectivity/wireless/performance

GET /copilot/connectivity/wireless/locations/time-to-connect

GET /copilot/connectivity/wireless/locations/quality-index

GET /copilot/connectivity/wireless/locations/performance

GET /copilot/connectivity/wireless/locations/events

GET /copilot/connectivity/wireless/experience

GET /copilot/connectivity/wireless/events

GET /copilot/connectivity/wireless/apps

copilot-anomalies

PUT /copilot/anomalies/update-device-action

PUT /copilot/anomalies/update-action

PUT /copilot/anomalies/devices/update-action

PUT /copilot/anomalies/devices/feedback

POST /copilot/anomalies/exclude-vlans

POST /copilot/anomalies/exclude-vlans-csv

GET /copilot/anomalies/wifi-efficiency/stats

GET /copilot/anomalies/wifi-efficiency/client-list

GET /copilot/anomalies/wifi-capacity/stats

GET /copilot/anomalies/wifi-capacity/client-list

GET /copilot/anomalies/report

GET /copilot/anomalies/port-efficiency/stats

GET /copilot/anomalies/port-efficiency/speed-duplex-stats

GET /copilot/anomalies/poeflapping/trends

GET /copilot/anomalies/poeflapping/stats

GET /copilot/anomalies/poeflapping/lldp-cdp-info

GET /copilot/anomalies/notifications

GET /copilot/anomalies/missing-vlan/count

GET /copilot/anomalies/locations

GET /copilot/anomalies/hardware-health/stats

GET /copilot/anomalies/hardware-health/cpu-mem-stats

GET /copilot/anomalies/hardware-health/client-list

GET /copilot/anomalies/excluded-vlans-list

GET /copilot/anomalies/dfs-recurrence/count-stats

GET /copilot/anomalies/dfs-recurrence/channel-stats

GET /copilot/anomalies/devices-with-locations

GET /copilot/anomalies/devices-by-location

GET /copilot/anomalies/anomalies-by-category

GET /copilot/anomalies/adverse-traffic/packet-counts

GET /copilot/anomalies/adverse-traffic/device-stats

copilot-anomalies:r

GET /copilot/anomalies/wifi-efficiency/stats
GET /copilot/anomalies/wifi-efficiency/client-list
GET /copilot/anomalies/wifi-capacity/stats
GET /copilot/anomalies/wifi-capacity/client-list
GET /copilot/anomalies/report
GET /copilot/anomalies/port-efficiency/stats
GET /copilot/anomalies/port-efficiency/speed-duplex-stats
GET /copilot/anomalies/poeflapping/trends
GET /copilot/anomalies/poeflapping/stats
GET /copilot/anomalies/poeflapping/lldp-cdp-info
GET /copilot/anomalies/notifications
GET /copilot/anomalies/missing-vlan/count
GET /copilot/anomalies/locations
GET /copilot/anomalies/hardware-health/stats
GET /copilot/anomalies/hardware-health/cpu-mem-stats
GET /copilot/anomalies/hardware-health/client-list
GET /copilot/anomalies/excluded-vlans-list
GET /copilot/anomalies/dfs-recurrence/count-stats
GET /copilot/anomalies/dfs-recurrence/channel-stats
GET /copilot/anomalies/devices-with-locations
GET /copilot/anomalies/devices-by-location
GET /copilot/anomalies/anomalies-by-category
GET /copilot/anomalies/adverse-traffic/packet-counts
GET /copilot/anomalies/adverse-traffic/device-stats

licenses

Permission not used

licenses:r

Permission not used

copilot-assurance-scans:r

GET /copilot/assurance-scans/overview

packet-capture

GET /packetcaptures
POST /packetcaptures
DELETE /packetcaptures
POST /packetcaptures/{id}/:upload
POST /packetcaptures/{id}/:stop
GET /packetcaptures/{id}
DELETE /packetcaptures/{id}

GET /packetcaptures/files

packet-capture:r

GET /packetcaptures

GET /packetcaptures/{id}

GET /packetcaptures/files

country

GET /countries

GET /countries/{countryCode}/:validate

GET /countries/{countryAlpha2Code}/states

country:r

GET /countries

GET /countries/{countryCode}/:validate

GET /countries/{countryAlpha2Code}/states

cas

Permission not used

cas:r

Permission not used

cas-policies

Permission not used

cas-policies:r

Permission not used

cas-metadata:r

Permission not used

cns-subscriptions

Permission not used

cns-subscriptions:r

Permission not used

hotspot-profile

GET /hotspot-profiles/{id}

PUT /hotspot-profiles/{id}

DELETE /hotspot-profiles/{id}

GET /hotspot-profiles

POST /hotspot-profiles

hotspot-profile:r

GET /hotspot-profiles/{id}

GET /hotspot-profiles

hotspot-service-provider-profile

GET /hotspot-service-provider-profiles/{id}

PUT /hotspot-service-provider-profiles/{id}

DELETE /hotspot-service-provider-profiles/{id}

GET /hotspot-service-provider-profiles

POST /hotspot-service-provider-profiles

hotspot-service-provider-profile:r

GET /hotspot-service-provider-profiles/{id}

GET /hotspot-service-provider-profiles

afc:relaxed_read

Permission not used

afc-filter-metadata:relaxed_read

POST /afc/filter-metadata

afc-export:relaxed_read

POST /afc/export

afc-reports:relaxed_read

Permission not used

floor-afc-details

GET /floor/afc/details

PUT /floor/afc/details

POST /floor/afc/details

DELETE /floor/afc/details/{id}

floor-afc-details:r

GET /floor/afc/details

rtts

POST /rtts

DELETE /rtts/{id}

rtts:r

Permission not used

ng-reports

GET /ng-reports/scheduled/{reportId}/recipients

PUT /ng-reports/scheduled/{reportId}/recipients

POST /ng-reports/scheduled/{reportId}/recipients
GET /ng-reports/scheduled/custom/{reportId}
PUT /ng-reports/scheduled/custom/{reportId}
POST /ng-reports/timeseries
POST /ng-reports/tabledata
GET /ng-reports/scheduled/custom
POST /ng-reports/scheduled/custom
DELETE /ng-reports/scheduled/custom
POST /ng-reports/metadata/user
POST /ng-reports/metadata/ssids
POST /ng-reports/metadata/os
POST /ng-reports/metadata/device
POST /ng-reports/metadata/client
POST /ng-reports/metadata/bands
POST /ng-reports/metadata/application
POST /ng-reports/downloads/reports
PATCH /ng-reports/scheduled/{reportScheduleId}
GET /ng-reports/scheduled/runs/{reportRunId}/recipients
GET /ng-reports/scheduled/reports/download
GET /ng-reports/scheduled/pci-compliance
GET /ng-reports/scheduled/network-summary
GET /ng-reports/scheduled/custom/{reportScheduleId}/runs
GET /ng-reports/information/{metrics}
GET /ng-reports/information/
GET /ng-reports/download/reports/{id}
DELETE /ng-reports/scheduled/runs

ng-reports:r

GET /ng-reports/scheduled/{reportId}/recipients
POST /ng-reports/scheduled/{reportId}/recipients
GET /ng-reports/scheduled/custom/{reportId}
POST /ng-reports/timeseries
POST /ng-reports/tabledata
GET /ng-reports/scheduled/custom
POST /ng-reports/scheduled/custom
POST /ng-reports/metadata/user
POST /ng-reports/metadata/ssids
POST /ng-reports/metadata/os
POST /ng-reports/metadata/device
POST /ng-reports/metadata/client
POST /ng-reports/metadata/bands
POST /ng-reports/metadata/application
POST /ng-reports/downloads/reports
GET /ng-reports/scheduled/runs/{reportRunId}/recipients
GET /ng-reports/scheduled/reports/download

GET /ng-reports/scheduled/pci-compliance
GET /ng-reports/scheduled/network-summary
GET /ng-reports/scheduled/custom/{reportScheduleId}/runs
GET /ng-reports/information/{metrics}
GET /ng-reports/information/
GET /ng-reports/download/reports/{id}

acct-api-token

GET /acct-api-token
POST /acct-api-token
DELETE /acct-api-token/{id}
PATCH /acct-api-token/{id}
GET /acct-api-token/export
DELETE /acct-api-token/:delete

acct-api-token:r

GET /acct-api-token
GET /acct-api-token/export

site-afc-schedule

GET /site/afc/schedule
PUT /site/afc/schedule
POST /site/afc/schedule

site-afc-schedule:r

GET /site/afc/schedule

ap-spectrum

POST /ap/spectrum/

ap-spectrum:r

Permission not used

afc-candidates

POST /afc/mobileapp/apcandidates

ng-scheduled-reports:w

PUT /ng-reports/scheduled/{reportId}/recipients
POST /ng-reports/scheduled/{reportId}/recipients
PUT /ng-reports/scheduled/custom/{reportId}
POST /ng-reports/scheduled/custom
DELETE /ng-reports/scheduled/custom
PATCH /ng-reports/scheduled/{reportScheduleId}
DELETE /ng-reports/scheduled/runs

ng-scheduled-get-reports:r

GET /ng-reports/scheduled/{reportId}/recipients
GET /ng-reports/scheduled/custom/{reportId}
GET /ng-reports/scheduled/custom
GET /ng-reports/scheduled/runs/{reportRunId}/recipients
GET /ng-reports/scheduled/reports/download
GET /ng-reports/scheduled/pci-compliance
GET /ng-reports/scheduled/network-summary
GET /ng-reports/scheduled/custom/{reportScheduleId}/runs

account-user-external

GET /users/external
POST /users/external
GET /users/external/{id}
DELETE /users/external/{id}
PATCH /users/external/{id}

account-user-me

GET /users/me

client-user-reports

GET /users/reports/{id}

account-user-id

GET /users/{id}

account-user-list

GET /users

account-user-create

POST /users

client-user-data-usage

POST /users/data-usage

client-user-filter-metadata

POST /users/filter-metadata

client-user-grid

POST /users/grid

client-user-grid-export

POST /users/grid-export

client-user-type-distribution

POST /users/type-distribution

account-user-modify

DELETE /users/{id}

PATCH /users/{id}