

Import facility structure

Instance Setup · ~20 min

BEFORE YOU START

- ☐ You've read **Before you begin** (you know your DHIS2 URL + credentials)
- ☐ You know which level in your DHIS2 hierarchy corresponds to *facility* (often level 4 or 5)

What you'll do

Pull your country's facility registry — every facility with its region and district — directly from DHIS2 into FASTR. The administrative areas are **derived automatically from the facility rows**: you never manage admin areas separately. After this, every analysis can disaggregate results by region, district, or facility.

1 Open the Facilities registry

1. Click **Data** in the top navigation. The page is organized into **General**, **HMIS**, **HFA**, and **ICEH** sections.
2. In the **HMIS** section, click the **Facilities** card.

Demonstration site → FASTR

Projects Data Results Assets Users EN Help

Data

General

Admin area labels
Not set — using default names

HMIS

Configuration Admin area depth: 4 Facility columns: 3	DHIS2 connection Server: https://api.mhch.org/ind...	Facilities Facilities: 107 Admin area 2: 5 Admin area 3: 16 Admin area 4: 19	Indicators Common indicators: 14 DHIS2 indicators: 9 Calculated indicators: 3	Data Not data
--	--	---	---	-------------------------

GeoJSON maps
No GeoJSON maps uploaded

HFA

Configuration Admin area depth: 4 Facility columns: 3	Facilities Facilities: 107 Admin area 2: 5	Time points Time points: 4	Sampling weights No weights imported	Indicators HFA indicators: 249
--	---	--------------------------------------	--	--

2 Import from DHIS2

Start a DHIS2 import from the Facilities page. The **stored DHIS2 connection** appears — the one set up once for the whole instance via **Manage connection**. Confirm it.

No stored connection yet? An administrator sets it up once — URL (with <https://>), username, password — and it is saved encrypted for the whole instance. Nobody re-types credentials after that.

3 Select the facility level

Select **Facility**. FASTR's analysis modules require facility-level data — they aggregate up from facilities to districts and regions internally, not the other way around. Selecting *Facility* brings all the levels above it (district, region, ...) along automatically.

Launch the import and wait for it to complete — usually 30 seconds to a few minutes depending on country size.

