readme.md 2024-03-05

README for DWP Module

This module consists of five MATLAB functions designed to perform wavelength and pixel conversions using a dispersion wavelength polynomial (DWP) fitting method. These functions are intended for use in optical and spectroscopy applications where precise mapping between pixel positions and wavelength values is required.

Author Information

Contributors: Wei-Hong Yeo, Benjamin Brenner

• Affiliation: Northwestern University, Department of Biomedical Engineering.

• Contact:

• Email: foil.northwestern@gmail.com

o GitHub: FOIL-NU

Functions Overview

- **dwp_fit**: Performs a linear fit to map between pixels and wavelengths using an initial guess and optional data exclusion.
- **dwp_fn**: Calculates the dispersion of the DWP module based on a rational function, suitable for converting wavelengths to pixels.
- **dwp_ifn**: Provides the inverse calculation of dwp_fn, converting pixels back to wavelengths.
- dwp_px2wl: Uses a fitting object to convert an array of pixel values into wavelengths.
- dwp_wl2px: Converts an array of wavelengths into pixel values using a fitting object.

Function Details

dwp_fit

- **Purpose**: Fits a linear model to a set of data points.
- Inputs:
 - w1: Vector of wavelengths.
 - o dis: Vector of dispersions (pixel values).
 - o param_guess: Initial guess for the fit parameters.
 - o excluded_data: Data points to exclude from the fit.
- Outputs:
 - fya: A fitting object for conversions.
 - o gof: Goodness-of-fit statistics.

dwp_fn

- Purpose: Calculates pixel dispersion based on a rational function.
- Input: x: Wavelength.
- **Output**: fx: Calculated dispersion.

dwp_ifn

• **Purpose**: Calculates the inverse of the dispersion function.

readme.md 2024-03-05

- Input: x: Dispersion.
- Output: gx: Corresponding wavelength.

dwp_px2wl

- Purpose: Converts pixels to wavelengths using a fitting object.
- Inputs:
 - px: Vector of pixels.
 - o fya: Fitting object.
- Output: wl: Vector of wavelengths.

dwp_wl2px

- Purpose: Converts wavelengths to pixels using a fitting object.
- Inputs:
 - wl: Vector of wavelengths.
 - fya: Fitting object.
- Output: px: Vector of pixels.

Additional Notes

- Ensure the input vectors for wavelengths and pixels are of the same length when using these functions.
- The dwp_fit function requires at least two inputs (wl and dis). Optional parameters include param_guess and excluded_data.
- The valid range for wavelength inputs in dwp_fn and dwp_ifn is 400nm to 900nm. Inputs outside this range may result in inaccurate conversions.

Usage Example

To fit a model and then convert between pixels and wavelengths:

```
[fitResult, gof] = dwp_fit(wavelengths, dispersions, [initialGuess]);
convertedWavelengths = dwp_px2wl(pixels, fitResult);
convertedPixels = dwp_wl2px(wavelengths, fitResult);
```

This README provides a basic overview of each function in the DWP module. Users are encouraged to review the function files for detailed comments and implementation notes.