#### You need to be in a LB Edit Suite

## A. Bounce your surround mix out of Pro Tools


- 1. File> bounce to disk
- 2. Change settings.



- 3. Convert after bounce
- 4. Save

# B. Creating an AC-3 File

- 1. Create a new Pro Tools session. 24 Bit Depth. 48k Sample Rate.
- 2. Import your six stems from the last step.



- 3. Click Add. Click Done.
- 4. Click New Track and Session Start. Click OK.
- 5. Select the audio in the timeline
- 6. Audio Suite> Sound Field> SoundCode Dolby Digital Encode


ENCODE **BSI EXT** 3/2 LCRLsRs 🔻 Film: Standard coding mode 448 kbps data rate dolby surround mode Complete Main 🔻 lowpass filter bitstream mode copyright original dialog norm Ife enable info exists mix level PUNCH IN/OUT IMPORT blahblahtest file name .ac3 type .wav type /Users/admin/Desktop

5. Set the Dolby Digital encoding parameters. Use settings below.

- 6. Set the output file name.
- 7. Click on the "Encode" button.

#### C. Photoshop

1. File> new> use settings below




- 2. Click OK.
- 3. On the toolbar, click on the "T" for text tool
- 4. Click and drag on your work area to create a textbox
- 5. Add the copyright information (STAN)
- 6. Format text and background however you like.
- 7. When you are finished making your slate go to File> Save As
- 8. Save the file. Format: JPEG. Click Save.
- 9. Hit OK.

#### D. Encore

- 1. Click New Project
- 2. Name your project and choose the save location. The rest stays the same. Press OK.
- 3. Menu> New Menu



- 4. File> Import As> Asset. Select your files (.ac3 and .mov or .mp4)
- 5. On the toolbar, click on the "T" for text tool
- 6. On the Menu, create a title for the DVD.
- 7. Create additional titles for Original, Stereo, and 5.1
- 8. On the toolbar, choose the Direct Select Tool and select Original. Object> Convert to button
- 9. Timeline> New Timeline. One for each title
- 10. Move the .ac3 and .mov/.mp4 to the timeline
- 11. Click on the Timeline in the Project Pane. In the Properties Pane, change the end action of the timeline to the Menu> Default




12. In the Project Pane double click on the Menu you created. Select the button and in the

# Properties Pane, change the Link to the Timeline> Chapter 1



- 13. Repeat steps 8-12 for each song.
- 14. Press the Preview button in the toolbar. And test the DVD. Exit here.
- 15. Click on the build tab



- 16. Change the Format to DVD and Output to DVD Disc
- 17. Name the DVD
- 18. Insert the DVD
- 19. Build

## **Test in DVD Player**