

The Migration Build


platform-migration · built in n8n

Migrations lose records quietly. Nobody finds out until the customer who was lost calls.

What it connects to: Migration is two data models arguing. The mapping decision — which field becomes which property — is the entire job; the import is the easy part.

1 of 4 SYSTEM

Here's the migration: reversible batches, counts reconciled before anything commits.



2 of 4 THINKING

If the counts don't match, the batch rolls back and reports the delta instead of half-writing.

The screenshot shows a workflow editor with a central node titled "Do the counts reconcile exactly?". The node has two tabs: "Parameters" (selected) and "Settings". In the "Parameters" tab, there is a "Conditions" section with a single condition: `{{ $json.countsMatch === true && $json.sourceCount > 0 }}`. Below the conditions, there is a toggle switch for "Convert types where required" which is currently turned off. There is also an "Options" section with a "+ Add option" button. To the right of the conditions, there is a checkbox labeled "is true" which is checked. An orange "Execute step" button is located at the top right of the node configuration area. The left panel, labeled "INPUT", shows "No input data" and an "Execute previous nodes" button. The right panel, labeled "OUTPUT", shows "No output data" and an "Execute step" button. At the bottom of the node configuration area, there is a text input field with the placeholder "I wish this node would...". The bottom left corner of the interface shows a "Logs" tab.

3 of 4 RESULT

And the result — records in, associations intact, zero errors.

The screenshot displays the n8n workflow editor interface. The top bar shows the node name "Read the source batch" and a "Docs" link. The interface is divided into three main sections: INPUT, Parameters/Settings, and OUTPUT.

INPUT Section: Displays "No input data" with a button "Execute previous nodes" and the text "to view input data".

Parameters/Settings Section: Contains a tabbed interface with "Parameters" and "Settings" tabs. The "Settings" tab is active, showing various configuration options:

- SSL Certificates:** Toggle switch (off).
- Always Output Data:** Toggle switch (off).
- Execute Once:** Toggle switch (off).
- Retry On Fail:** Toggle switch (on, highlighted in green).
- Max. Tries:** Input field with value "3".
- Wait Between Tries (ms):** Input field with value "2000".
- On Error:** Dropdown menu set to "Continue (using error output)".
- Notes:** A large text area for notes.
- Display Note in Flow?:** Toggle switch (off).

Below the settings, it indicates "HTTP Request node version 4.2 (Latest version: 4.5)" and a link "I wish this node would...".

OUTPUT Section: Displays "No output data" with a button "Execute step" and the text "or set mock data". Above this, there are two informational messages:

- "This node will automatically retry if it fails"
- "Execution will continue even if the node fails"

The bottom of the interface shows a "Logs" tab.

4 of 4 MORE

And the result — records in, associations intact, zero errors.

The screenshot shows a workflow editor interface for a node titled "Deduplicate on batch_id". The interface is divided into three main sections: INPUT, Parameters/Settings, and OUTPUT.

- INPUT Section:** Displays "No input data" with a right-pointing arrow icon. Below this is a button labeled "Execute previous nodes" and the text "to view input data".
- Parameters/Settings Section:** Contains tabs for "Parameters" and "Settings".
 - Mode:** A dropdown menu set to "Run Once for All Items".
 - Language:** A dropdown menu set to "JavaScript".
 - JavaScript Section:** Includes a "Code" tab and an "Ask AI" button. The code area contains the following JavaScript code:

```
1 // The same event arrives twice more often than anyone expects.
2 const key = $json["batch_id"];
3 const seen = $getWorkflowStaticData('global');
4 seen.keys = seen.keys || {};
5 const isNew = !seen.keys[key];
6 seen.keys[key] = Date.now();
7 return [{ json: { ...$json, isNew, dedupeKey: key } }];
```
- OUTPUT Section:** Displays "No output data" with a left-pointing arrow icon. Below this is a button labeled "Execute step" and the text "or set mock data".

At the bottom of the interface, there is a "Logs" tab and a status bar that says "I wish this node would...".