

The Reconciliation Build


books-reconciliation · built in n8n

The hours don't go into the matching. They go into the handful of rows a human has to judge.

What it connects to: The payout processor and the ledger disagree by design — fees, timing, refunds. Reconciliation is not a report, it is a translation layer between two systems that count differently.

1 of 4 SYSTEM

Here's the system: payouts in, matched to the cent, and only the exceptions reach a person.



2 of 4 THINKING

This is what it reports weekly — what's still unreconciled and how old, because that's the number that turns into a month-end problem.

Does it match to the cent?

INPUT

→|

ParametersSettings

Execute step

Conditions

fx

{{ \$json.matched === true && Math.abs(\$json.delta) < 0.01 }}

is true

+ Add condition


☐ Convert types where required

Options

+ Add option

3 of 4 THEIR-WORLD

The same logic inside QuickBooks — a rule that encodes the ruling once instead of every week.



4 of 4 MORE

And the variance it's built to close: the ledger and the bank disagreeing, in one frame.

The screenshot displays the n8n workflow editor interface. The top bar shows the node name 'Pull the open invoices' and a 'Docs' link. The interface is divided into three main sections: INPUT, Parameters/Settings, and OUTPUT.

INPUT Section: Displays 'No input data' with a button 'Execute previous nodes' and the text 'to view input data'.

Parameters/Settings Section: Contains various configuration options:

- Parameters:** Includes toggle switches for 'SSL Certificates', 'Always Output Data', 'Execute Once', and 'Retry On Fail' (which is currently turned on).
- Max. Tries:** A numeric input field set to '3'.
- Wait Between Tries (ms):** A numeric input field set to '2000'.
- On Error:** A dropdown menu set to 'Continue (using error output)'.
- Notes:** A large text area for adding notes.
- Display Note in Flow?:** A toggle switch that is currently turned off.
- Version:** A footer note stating 'HTTP Request node version 4.2 (Latest version: 4.5)'.
- Footer:** A link that says 'I wish this node would...'.

OUTPUT Section: Displays 'No output data' with a button 'Execute step' and the text 'or set mock data'. Above this, there are two informational messages: 'This node will automatically retry if it fails' and 'Execution will continue even if the node fails'.

The bottom of the interface features a 'Logs' tab.