

The Reporting Layer


reporting · built in n8n

Most dashboards lie by omission. A zero that means 'unknown' looks exactly like a zero that means zero.

What it connects to: Every source counts a lead slightly differently. The reporting layer is where you decide, once and in writing, whose definition wins.

1 of 4 SYSTEM

Here's the system that gathers from every source and only publishes once there's enough data to be honest.



2 of 4 THINKING

Below the threshold it prints COLLECTING rather than a number that reads as fact.

 Is there enough data to be honest?

INPUT

ParametersSettings

Execute step

Conditions

fx

`{{ $json.n >= 30 && $json.sourcesRead == $json.sourcesExpected }}`

+ Add condition

☐ is true

Convert types where required


Options

+ Add option

→|

3 of 4 THEIR-WORLD

The reporting layer running live on real records.



4 of 4 MORE

And the same layer on a second stack — the numbers move, the structure does not.

The screenshot displays the n8n workflow editor interface. At the top, a node titled "Gather the numbers from every source" is selected. The interface is divided into three main sections: INPUT, Parameters/Settings, and OUTPUT.

INPUT Section: Shows "No input data" with a button "Execute previous nodes" and the text "to view input data".

Parameters/Settings Section: Contains various configuration options for the node:

- SSL Certificates:** Toggle switch (off).
- Always Output Data:** Toggle switch (off).
- Execute Once:** Toggle switch (off).
- Retry On Fail:** Toggle switch (on, highlighted in green).
- Max. Tries:** Input field with the value "3".
- Wait Between Tries (ms):** Input field with the value "2000".
- On Error:** Dropdown menu set to "Continue (using error output)".
- Notes:** A large text area for adding notes.
- Display Note in Flow?:** Toggle switch (off).
- Version:** HTTP Request node version 4.2 (Latest version: 4.5).
- Footer:** A link "I wish this node would..." is visible at the bottom.

OUTPUT Section: Shows "No output data" with a button "Execute step" and the text "or set mock data". Above this, there are two informational messages: "This node will automatically retry if it fails" and "Execution will continue even if the node fails".

The interface also includes a sidebar on the left with various icons and a "Logs" section at the bottom left.