## Skip to content CopyScaleConstraint(Constraint)

```
base\ classes -- \ \texttt{bpy\_struct}\ , \ \texttt{Constraint}
class bpy.types.CopyScaleConstraint(Constraint)
     Copy the scale of the target
     power
          Raise the target's scale to the specified power
          TYPE:
               float in [-inf, inf], default 1.0
     subtarget
          Armature bone, mesh or lattice vertex group, ...
          TYPE:
               string, default ", (never None)
     target
          Target object
          TYPE:
               Object
      use_add
          Use addition instead of multiplication to combine scale (2.7 compatibility)
          TYPE:
               boolean, default False
     use make uniform
          Redistribute the copied change in volume equally between the three axes of the owner
          TYPE:
               boolean, default False
     use offset
          Combine original scale with copied scale
          TYPE:
               boolean, default False
     use x
          Copy the target's X scale
          TYPE:
               boolean, default False
      use_y
          Copy the target's Y scale
          TYPE:
               boolean, default False
```

```
Copy the target's Z scale
   TYPE:
        boolean, default False
classmethod bl_rna_get_subclass(id, default=None)
   PARAMETERS:
        id(str) – The RNA type identifier.
   RETURNS:
        The RNA type or default when not found.
   RETURN TYPE:
        bpy.types.Struct subclass
classmethod bl_rna_get_subclass_py(id, default=None)
   PARAMETERS:
        id (str) – The RNA type identifier.
   RETURNS:
        The class or default when not found.
   RETURN TYPE:
        type
```

## **Inherited Properties**

•	<pre>bpy_struct.id_data</pre>	Constraint.mute
•	Constraint.name •	Constraint.enabled
•	Constraint.type •	Constraint.show_expanded
•	Constraint.is_override_data •	Constraint.is_valid
•	Constraint.owner_space •	Constraint.active
•	Constraint.target_space •	Constraint.influence
•	Constraint.space_object •	Constraint.error_location
•	Constraint.space_subtarget •	Constraint.error_rotation

## **Inherited Functions**

•	<pre>bpy_struct.as_pointer</pre>	•	<pre>bpy_struct.keyframe_delete</pre>
•	bpy_struct.driver_add	•	<pre>bpy_struct.keyframe_insert</pre>
•	bpy_struct.driver_remove	•	bpy_struct.keys
•	bpy_struct.get	•	<pre>bpy_struct.path_from_id</pre>
•	<pre>bpy_struct.id_properties_clear</pre>	•	bpy_struct.path_resolve
•	<pre>bpy_struct.id_properties_ensure</pre>	•	bpy_struct.pop
•	bpy_struct.id_properties_ui	•	<pre>bpy_struct.property_overridable_library_set</pre>
•	<pre>bpy_struct.is_property_hidden</pre>	•	<pre>bpy_struct.property_unset</pre>
•	<pre>bpy_struct.is_property_overridable_library</pre>	•	bpy_struct.type_recast
•	<pre>bpy_struct.is_property_readonly</pre>	•	bpy_struct.values
•	bpy_struct.is_property_set	•	Constraint.bl_rna_get_subclass
•	bpy struct.items	•	Constraint.bl rna get subclass py

Copyright © Blender Authors Made with Furo

Previous CopyRotationConstraint(Constraint) Report issue on this page