GeometryNodeInputMaterialIndex(GeometryNode)

```
base classes — bpy_struct, Node, NodeInternal, GeometryNode
```

class bpy.types.GeometryNodeInputMaterialIndex(GeometryNode)

Retrieve the index of the material used for each element in the geometry's list of materials

classmethod is_registered_node_type()

True if a registered node type

RETURNS:

Result

RETURN TYPE:

boolean

classmethod input template(index)

Input socket template

PARAMETERS:

index (int in [0, inf]) – Index

RETURNS:

result

RETURN TYPE:

NodeInternalSocketTemplate

classmethod output_template(index)

Output socket template

PARAMETERS:

index (int in [0, inf]) – Index

RETURNS:

result

RETURN TYPE:

NodeInternalSocketTemplate

classmethod bl rna get subclass(id, default=None)

PARAMETERS:

id(str) – The RNA type identifier.

RETURNS:

The RNA type or default when not found.

RETURN TYPE:

bpy.types.Struct subclass

classmethod bl rna get subclass py(id, default=None)

PARAMETERS:

id(str) – The RNA type identifier.

RETURNS:

The class or default when not found.

RETURN TYPE:

tyne

Inherited Properties

- bpy struct.id data
- Node.type
- Node.location
- Node.location absolute Node.hide
- Node.width
- Node.height
- Node.dimensions
- Node.name
- Node.label
- Node.inputs
- Node.outputs
- Node.internal links
- Node.parent
- Node.warning_propagation Node.bl_width_max
- Node.color
- Node.color_tag

- Node.select
- Node.show options
- Node.show preview
- Node.mute
- Node.show texture
- Node.bl idname
 - Node.bl label
- Node.bl description
- Node.bl icon
- Node.bl static type
- Node.bl width default
 - Node.bl width min
- Node.use custom color Node.bl height default
 - Node.bl height min
 - Node.bl_height_max

Inherited Functions

- bpy struct.as pointer
- bpy struct.driver add
- bpy struct.driver remove
- bpy_struct.get
- bpy struct.id properties clear
- bpy struct.id properties ensure
- bpy struct.id properties ui
- bpy_struct.is_property_hidden
- bpy_struct.is_property_overridable_library
- bpy struct.is property readonly
- bpy struct.is property set
- bpy struct.items
- bpy struct.keyframe delete
- bpy_struct.keyframe_insert
- bpy struct.keys
- bpy struct.path from id
- bpy_struct.path_resolve
- bpy struct.pop
- bpy_struct.property_overridable_library_set
- bpy struct.property unset
- bpy struct.type_recast
- bpy_struct.values
- Node.socket value update
- Node.is registered node type

- Node.poll instance
- Node.update
- Node.insert link
- Node.init
- Node.copy
- Node.free
- Node.draw buttons
- Node.draw buttons ext
- Node.draw label
- Node.debug zone body lazy function graph
- Node.debug_zone_lazy_function_graph
- Node.poll
- Node.bl_rna_get_subclass
- Node.bl rna get subclass py
- NodeInternal.poll
- NodeInternal.poll instance
- NodeInternal.update
- NodeInternal.draw buttons
- NodeInternal.draw buttons ext
- NodeInternal.bl rna get subclass
- NodeInternal.bl_rna_get_subclass_py
- GeometryNode.poll
- GeometryNode.bl_rna_get_subclass

• Node.poll

Previous GeometryNodeInputMaterial(GeometryNode) Report issue on this page Copyright © Blender Authors Made with Furo No GeometryNodeInputMeshEdgeAngle(GeometryNodeInputMeshEdgeAng