
Skip to content Falloff

The Falloff allows you to control the *Strength* falloff of the brush. The falloff is mapped from the center of the brush (left part of the curve) towards its borders (right part of the curve). Changing the shape of the curve will make the brush softer or harder. Read more about using the Curve Widget.




Brush curve example.

Curve Preset

Custom:

You can choose how the strength of the falloff is determined from the center of the brush to the borders by manually manipulating the control points within the curve widget. There are also a couple of preset custom curves displayed at the bottom of the curve widget that can be use on their own or as a starting point for tweaking.



Smooth:

The center strenoth the horder strenoth and the falloff transition between them are evenly distributed

THE CORE SUCHER IN COLOR SUCHER HIS HE HEST HERST CHICARIT CONTROL HEITHER CYCLES ABBRICAGE.

Smoother:

Similar to *Smooth* but produces a wider center point of the brush before tapering off.

Sphere:

The strength of the brush is predominately at its strongest point with a steep falloff near the border of the brush.

Root:

Similar to a Sphere but the center is a more concentrated point.

Sharp:

The center of the brush is the strongest point then exponentially tapers off to a lower strength, creating a fine point.

Linear:

With the center being the strongest, the strength will consistently weaken as it reaches the border of the brush.

Sharper:


Similar to *Sharp* but the center point is more condensed.

Inverse Square:

A hybrid between Smooth and Sphere.

Constant:

The strength of the brush remains unified across the entire brush. This will create a sharp edge at the border of the brush.



(From Left to Right) Smooth, Smoother, Sphere, Root, Sharp, Linear, Sharper, Inverse square, Constant.

Falloff Shape

Use projected or spherical falloff. Note, this is not supported in Texture Paint Mode.

Sphere:

Applies brushes influence in a sphere, outwards from the center.

Projected:

This turns the brush influence into a cylinder (the depth along the view is ignored) instead of a sphere. It can be used along the outline of a mesh to adjust its silhouette.

Front-Face Falloff

As faces point away from the view the brush strokes fade away to prevent harsh edges.

Normal Falloff / Front-Face Falloff

If disabled, the normal of the surface has no effect on the falloff.

Augic

The angle at which the falloff begins.

Previous Stroke Copyright ©: This page is licensed under a CC-BY-SA 4.0 Int. License Made with Furo Last updated on 2025-05-10

No Curs

View Source View Translation Report issue on this page