NodeTreeInterfaceSocketVectorVelocity(NodeTreeInterfaceSocket

```
base\ classes -- \verb|bpy_struct|, \verb|NodeTreeInterfaceItem|, \verb|NodeTreeInterfaceSocket|
class\ bpy.types. Node Tree Interface Socket Vector Velocity (Node Tree Interface Socket)
    3D vector socket of a node
     default value
         Input value used for unconnected socket
         TYPE:
              mathutils. Vector of 3 items in [-inf, inf], default (0.0, 0.0, 0.0)
     max_value
         Maximum value
         TYPE:
              float in [-inf, inf], default 0.0
     min_value
         Minimum value
         TYPE:
              float in [-inf, inf], default 0.0
     subtype
         Subtype of the default value
         TYPE:
              enum in ['DEFAULT'], default 'DEFAULT'
     draw(context, layout)
         Draw interface socket settings
         PARAMETERS:
              layout (UILayout, (never None)) - Layout, Layout in the UI
     init socket(node, socket, data path)
         Initialize a node socket instance
         PARAMETERS:
           • node (Node, (never None)) - Node, Node of the socket to initialize
           • socket (NodeSocket, (never None)) - Socket, Socket to initialize
           • data_path (string, (never None)) – Data Path, Path to specialized socket data
     from socket(node, socket)
         Setup template parameters from an existing socket
         PARAMETERS:
           • node (Node, (never None)) - Node, Node of the original socket
           • socket (NodeSocket, (never None)) - Socket, Original socket
```

classmethod bl_rna_get_subclass(id, default=None)

DAD AMETEDS.

```
I ANAIVILILINO.
```

id (str) – The RNA type identifier.

RETURNS:

The RNA type or default when not found.

RETURN TYPE:

bpy.types.Struct subclass

classmethod bl_rna_get_subclass_py(id, default=None)

PARAMETERS:

id(str) – The RNA type identifier.

RETURNS:

The class or default when not found.

RETURN TYPE:

type

Inherited Properties

- bpy_struct.id data
- NodeTreeInterfaceItem.item_type
- NodeTreeInterfaceItem.parent
- NodeTreeInterfaceItem.position
- NodeTreeInterfaceItem.index
- NodeTreeInterfaceSocket.name
- NodeTreeInterfaceSocket.identifier
- NodeTreeInterfaceSocket.description
- NodeTreeInterfaceSocket.socket_type
- NodeTreeInterfaceSocket.in_out

- NodeTreeInterfaceSocket.hide value
- NodeTreeInterfaceSocket.hide in modifier
- NodeTreeInterfaceSocket.force non field
- NodeTreeInterfaceSocket.is inspect output
- NodeTreeInterfaceSocket.layer selection field
- NodeTreeInterfaceSocket.attribute domain
- NodeTreeInterfaceSocket.default attribute name
- NodeTreeInterfaceSocket.default_input
- NodeTreeInterfaceSocket.bl_socket_idname

Inherited Functions

- bpy struct.as pointer
- bpy struct.driver add
- bpy_struct.driver remove
- bpy struct.get
- bpy_struct.id_properties_clear
- bpy struct.id properties ensure
- bpy_struct.id_properties_ui
- bpy struct.is property hidden
- bpy_struct.is_property_overridable_library
- bpy_struct.is_property_readonly
- bpy struct.is property set
- bpy_struct.items
- bpy struct.keyframe delete
- bpy struct.keyframe insert
- bpy_struct.keys

- bpy_struct.path_from_id
- bpy_struct.path_resolve
- bpy struct.pop
- bpy struct.property overridable library set
- bpy struct.property unset
- bpy_struct.type_recast
- bpy_struct.values
- NodeTreeInterfaceItem.bl rna get subclass
- NodeTreeInterfaceItem.bl_rna_get_subclass_py
- NodeTreeInterfaceSocket.draw
- NodeTreeInterfaceSocket.init socket
- NodeTreeInterfaceSocket.from socket
- NodeTreeInterfaceSocket.bl rna get subclass
- NodeTreeInterfaceSocket.bl rna get subclass

 $\begin{tabular}{ll} Previous & Copyright @ NodeTreeInterfaceSocketVectorXYZ (NodeTreeInterfaceSocketVectorXYZ) & NodeTreeInterfaceSocketVectorXYZ (NodeTreeInterfaceSocketVectorXYZ) & Blender & B$

Authors Made with Furo

Report issue on this page