#### Skip to content

# NodeTreeInterfaceSocketShader(NodeTreeInterfaceSocket)

base classes — bpy\_struct, NodeTreeInterfaceItem, NodeTreeInterfaceSocket

## class bpy.types.NodeTreeInterfaceSocketShader(NodeTreeInterfaceSocket)

Shader socket of a node

## draw(context, layout)

Draw interface socket settings

#### **PARAMETERS:**

layout (UILayout, (never None)) - Layout, Layout in the UI

#### init socket(node, socket, data path)

Initialize a node socket instance

#### **PARAMETERS:**

- node (Node, (never None)) Node, Node of the socket to initialize
- socket (NodeSocket, (never None)) Socket, Socket to initialize
- data\_path (string, (never None)) Data Path, Path to specialized socket data

## from\_socket(node, socket)

Setup template parameters from an existing socket

## **PARAMETERS:**

- node (Node, (never None)) Node, Node of the original socket
- socket (NodeSocket, (never None)) Socket, Original socket

## classmethod bl\_rna\_get\_subclass(id, default=None)

## **PARAMETERS:**

id (str) – The RNA type identifier.

#### **RETURNS:**

The RNA type or default when not found.

#### **RETURN TYPE:**

bpy.types.Struct subclass

## classmethod bl\_rna\_get\_subclass\_py(id, default=None)

## **PARAMETERS:**

id(str) – The RNA type identifier.

#### **RETURNS:**

The class or default when not found.

#### **RETURN TYPE:**

type

## **Inherited Properties**

- bpy\_struct.id\_data
- NodeTreeInterfaceItem.item\_type
- NodeTreeInterfaceItem.parent
- NodeTreeInterfaceItem.position
- NodeTreeInterfaceSocket.hide\_value
- NodeTreeInterfaceSocket.hide in modifier
- NodeTreeInterfaceSocket.force non field
- NodeTreeInterfaceSocket.is inspect output

- NodeTreeInterfaceItem.index
- NodeTreeInterfaceSocket.name
- NodeTreeInterfaceSocket.identifier
- NodeTreeInterfaceSocket.description
- NodeTreeInterfaceSocket.socket type
- NodeTreeInterfaceSocket.in out
- NodeTreeInterfaceSocket.layer selection field
- NodeTreeInterfaceSocket.attribute domain
- NodeTreeInterfaceSocket.default attribute name
- NodeTreeInterfaceSocket.default input
- NodeTreeInterfaceSocket.bl socket idname

## **Inherited Functions**

- bpy struct.as pointer
- bpy\_struct.driver\_add
- bpy struct.driver remove
- bpy struct.get
- bpy\_struct.id\_properties\_clear
- bpy struct.id properties ensure
- bpy struct.id properties ui
- bpy struct.is property hidden
- bpy\_struct.is\_property\_overridable\_library
- bpy struct.is property readonly
- bpy\_struct.is\_property\_set
- bpy struct.items
- bpy struct.keyframe delete
- bpy struct.keyframe insert
- bpy struct.keys

- bpy struct.path from id
- bpy struct.path resolve
- bpy struct.pop
- bpy struct.property overridable library set
- bpy\_struct.property\_unset
- bpy struct.type recast
- bpy struct.values
- NodeTreeInterfaceItem.bl rna get subclass
- NodeTreeInterfaceItem.bl rna get subclass py
- NodeTreeInterfaceSocket.draw
- NodeTreeInterfaceSocket.init socket
- NodeTreeInterfaceSocket.from socket
- NodeTreeInterfaceSocket.bl rna get subclass
- NodeTreeInterfaceSocket.bl rna get subclass

Previous

NodeTreeInterfaceSocketRotation(NodeTreeInterfaceSocket)

Report issue on this page

Copyright © Blender Authors NodeTreeInterfaceSocketString(NodeTreeInterfaceSock Made with Furo

No