# Skip to content **Precision**

Reference

Mode:

Object and Edit Modes

**Shortcut:** 

Ctrl and/or Shift

Holding Ctrl during a transform operation (such as move, rotate or scale) will toggle Transform Snapping. When using Increment Snap this allows the transformation to be performed in discrete amounts.

Holding Shift during a transform operation will transform the object at 1/10th the speed, allowing much finer control.

The magnitude of the transformation can be viewed in the 3D Viewport header. Releasing <code>Ctrl</code> or <code>Shift</code> during the transformation will cause the movement to revert back to its normal mode of operation.

Note

The snapping behaviors described on this page only apply when Increment Snap is selected.

Tip

It is possible to enable both snapping and precision mode, simply hold Ctrl and Shift. This has the following effects:

Move

Changes in 0.1 unit increments, regardless of zoom level.

**Rotation** 

Changes in 1 unit increments.

Scale

Changes in 0.01 unit increments.

# **Usage**

## With Hotkeys

Press G, R or S and then hold either Ctrl, Shift or Shift - Ctrl.

## With the Transform Gizmo

Select the gizmo handle then while moving the mouse hold Ctrl, Shift or Shift - Ctrl to activate precision control or snapping.

See also

Read more about the Transform Gizmo.

Tip


Combining with Other Controls

All of the precision controls detailed on the page can be combined with the Axis Locking controls and used with the different Pivot Points.

# **Snapping**

111010

Snapping while moving objects changes the object location in 1 unit increments. While in an aligned view, The increment amount is changed based on the zoom level. For example, at a base zoom level objects are moved in increments of 1 unit (i.e. between the two light gray lines). Zooming in enough to see the next set of gray lines will snap in increments of 1/10 of a unit. Zooming in further until will snap in increments of 1/100 of a unit and so on until the zoom limit is reached. Zooming out will have the opposite effect and cause movement to happen by increments of 10, 100 units, etc.



One unit (default zoom level).

#### **Rotation**

Holding Ctrl will cause rotations of 5 degrees.

### **Scale**

Holding Ctrl will cause size changes in increments of 0.1 units.

Note

Snapping Modes

Note that when you are Snapping To something other than *Increment*, holding Ctrl will cause the selection to snap to that nearest element.

Read more about snapping.

# **Precision**

Holding Shift during transformations allows for very fine control that does not rely on fixed increments. Rather, large movements of the mouse across the screen only result in small transformations of the selection.

In rotation mode the selected element will be rotate in 0.01 degree increments.

Previous Axis Locking Copyright ©: This page is licensed under a CC-BY-SA 4.0 Int. License Made with Furo

Last updated on 2025-05-10

View Source View Translation Report issue on this page No Mo