

一句话生硬件-相关资料文档

upypi API接口和thonny-upypi-manager包管理插件

查看：[📖 Thonny-uPyPi 包管理插件需求规格说明书](#)



thonny-upypi-manager包管理插件代码如下：



thonny-upypi-manager-main.rar

60.33KB



使用可看：

[📖 Thonny中Mpy包管理器插件的安装和使用](#)

skill相关仓库

https://github.com/FreakStudioCN/MicroPython_Skills



mpremote调试相关

看skill:https://github.com/FreakStudioCN/MicroPython_Skills



和仓库:

<https://github.com/micropython/micropython/blob/master/tools/mpremote/README.md>

The screenshot shows a GitHub web interface for the `micropython / micropython` repository. The left sidebar displays the file tree with folders like `.github`, `docs`, `drivers`, `examples`, `extmod`, `lib`, `logo`, `mpy-cross`, `ports`, `py`, `shared`, `tests`, and `tools`. The `tools` folder is expanded, showing subfolders like `autobuild`, `make_pinout_diagram`, `mpremote`, `tests`, and files like `.gitignore`, `LICENSE`, `README.md`, `mpremote.py`, and `pyproject.toml`. The main content area shows the `README.md` file for the `mpremote` tool, which is a CLI tool for remote control of MicroPython devices. The README includes a description, a simple usage example, and a full list of supported commands with their options.

mpremote -- MicroPython remote control

This CLI tool provides an integrated set of utilities to remotely interact with and automate a MicroPython device over a serial connection.

The simplest way to use this tool is:

```
mpremote
```

This will automatically connect to a USB serial port and provide an interactive REPL.

The full list of supported commands are:

```
mpremote connect <device>      -- connect to given device
                                device may be: list, auto, id:x, port:x
                                or any valid device name/path
mpremote disconnect            -- disconnect current device
mpremote mount <local-dir>      -- mount local directory on device
mpremote eval <string>          -- evaluate and print the string
mpremote exec <string>          -- execute the string
mpremote run <file>             -- run the given local script
mpremote fs <command> <args...> -- execute filesystem commands on the device
                                command may be: cat, ls, cp, rm, mkdir, rmdir, sha256sum
                                use ":" as a prefix to specify a file on the device
mpremote repl                  -- enter REPL
                                options:
                                --capture <file>
                                --inject-code <string>
                                --inject-file <file>
mpremote mip install <package...> -- Install packages (from micropython-lib or third-party sources)
                                options:
                                --target <path>
                                --index <url>
```

CI/CD 自动同步流程-相关子模块

<https://github.com/MicroPythonOS/MicroPythonOS>

https://github.com/lvgl-micropython/lvgl_micropython

<https://github.com/micropython/micropython>

<https://github.com/espressif/esptool>

<https://github.com/FreakStudioCN/upypi>