


Bluebell and X-CSL lights updater for XP12

Inhaltsverzeichnis

Files in this package.....	2
Quickstart tl;dr.....	3
Prerequisites:.....	3
What is it?.....	4
Installation:.....	4
!! First of all !!.....	4
!! Make a backup of your CSL directories !!.....	4
How to:.....	5
Normal start.....	5
Start with parameters explained.....	5
-h or -- help: show help page.....	5
-v or -- version: show program version.....	5
-p or -- path: set path with argument.....	5
-u or -- undo: undo previous conversion.....	5
-r or -- remove-backups: remove backup files.....	5
f or - -flashing-beacons: Creates flashing beacons.....	5
Redo (with new params)?.....	6
Typical examples:.....	6
Show usage.....	7
Tested on:.....	7
How does it work?.....	8
How long does it take to convert?.....	8
Specials.....	9
aircrafts.json.....	9
light_params.json.....	9
Typo's:.....	9
Custom CSL aircraft:.....	9
License.....	10

Files in this package



Quickstart tl;dr

Prerequisites:

Python must be installed. It runs with:

Python 3.10 on Linux

Python 3.12 on Windows 10

Python 3.13 on Windows 11

For Bluebell packages make sure you have the version from x-plane.org.

- **Make a backup of your CSL directories prior to changing your files!**
- **Some custom CSL objects will end up with no lights at all or only some lights are available and others don't. Caused by incomplete or inappropriate light params which get removed in the conversion process.**

And then, lets go!!

1. Unzip the file to a place of choice
2. Edit the configs/config.ini and set the csl_path value.
3. Start the tool with ./lights_updater.py or
4. Start the tool with ./lights_updater.py -h for help on the command line parameters and / or in case you don't use the config file.
5. See also page 6, especially Typical examples for more info.

Notice!

The path must contain at least one xsb_aircraft.txt as this is the base from where the tool creates the paths to the aircraft object files. It's the same as LiveTraffic and I believe also xPilot do.

Path in config.ini should be in quotation marks!! Newest version also works without them.

Path on the command line MUST have quotes if there are (white-)spaces in the path!!

What is it?

I use LiveTraffic and I really like it. But! When I am at the holding point of a runway and I look if someone is on final, I don't see anything at daylight or the plane must be that close that you can see its body. So a (fast) plane on final can be missed. Yes, sure, you can use ATC, but I do not do that for every flight. Even planespotting is less nice if you cannot spot the planes in line as they are closing to the runway. See the screenshots. I am not patient enough to change all the objects by hand to convert them to the new XP12 light params. That was the reason to build this tool. And I learned more about programming in Python. Double win!

X-CSL and Bluebell still have the "old" XP11 lightparams in the aircraft objects. This tool changes them to XP12 params.

I change only the "necessary" lights: Landing lights, taxi lights, nav lights, beacon and strobe lights. All other lights are untouched.

Installation:

!! First of all !!

!! Make a backup of your CSL directories !!

1. It's always a good habit to make a backup of things you are going to change.
2. Copy the zip to destination of your choice
3. Unzip the file
4. Edit and set the path to your CSL resources directory in the config ini.

```
[csl]  
; Example: csl_path = /path/to/XP12/plugins/directory/LiveTraffic/Resources/CSL  
csl_path = D:/path/to/your/X-Plane 12/Resources/plugins/LiveTraffic/Resources/CSL
```

Notice!

The path must contain at least one `xsb_aircraft.txt` as this is the base from where the tool creates the paths to the aircraft object files. It's the same as LiveTraffic and I believe also xPilot do.

5. Run it. See for more info on the next page!

How to:

Just start it with either:

```
python lights_updater.py  
Or  
./lights_updater.py  
Or  
python.exe lights_updater.py
```

Normal start

No arguments! But the path to the cls file must be set in the config.ini!

Start with parameters explained

-h or -- help: show help page.

-v or -- version: show program version

-p or -- path: set path with argument

You can specify a path besides the setting in the config.ini with **-p** or **--path** and the path to your csl file in quotes.

For example: ./lights-updater.py -p "[D:\X-Plane 12\Resources\etc\etc](#)" **Path on the command line MUST have quotes if there are (white-)spaces in the path!!-**

-f or --flashing-beacons: Creates flashing beacons

Nowadays, the bigger airplanes have flashing beacons. This will simulate that.

-u or -- undo: undo previous conversion

This tool makes a backup of each object file that is in the xsb_aircrafts.txt, so there is an option to undo the changes with the **-u**, or **--undo** option.

-r or -- remove-backups: remove backup files

If all is good, there is a option to delete the backups after all is fine. This can be done by starting the tool with the **-r** or **--remove-backups** option. **But be careful. Gone is gone. At least on Linux.**

Redo (with new or changed light params)?

You can restart the tool if you change values in the light_params.json.

But! Switching between normal beacons and flashing will not work.

Recommended workflow is always to first run undo and run the conversion.

Typical examples:

A typical command line to process CSL files will look like this:

```
python ./lights_updater.py -p "/c:/X-Plane 12/Resources/plugins/LiveTraffic/Resources/CSL"
```

With the undo function:

```
python ./lights_updater.py -p "/c:/X-Plane 12/Resources/plugins/LiveTraffic/Resources/CSL" -u
```

Show usage

The usage can be viewed when you start the tool with the **-h** or **--help** option.

usage: Lights updater for CSL objects [-h] [-p path] [-f] [-u] [-r] [-v]

This program can convert XP11 lightparams of CSL aircraft objects to the new XP12 specifications.

Developed for getting landing lights for LifeTraffic.

Works with Bluebell and X-CSL packages.

Works with some custom CSL aircraft, but with limitations. The quality of light params in those model vary a lot.

For normal start you don't need any arguments.

But then you **MUST** specify the csl_path in the config.ini file!

Optional arguments:

- h, --help show this help message and exit
- p path, --path path Set path to location of CSL aircrafts.
If there are whitespaces in the path,
you **MUST** use quotation marks around the path!
To be save: Always use them.
- f, --flashing-beacons Sets the beacons to be flashing beacons on bigger airplanes!
- u, --undo Rolls back the previous made changes!
- r, --remove-backups Removes the backup files. Be careful!
- v, --version show program's version number and exit

!!Attention!!

If you specify a path with -p / --path when processing the objects and you want to undo your changes,

or remove the backup files with -r / --remove-backups, you need the specify the path again!

If you don't and there is a path specified in the config.ini, results may not be what you expected!

Now you know!

Tested on:

- Python 3.10 on Linux
- Python 3.12 on Windows 10
- Python 3.13 on Windows 11
- Bluebell packages
- X-CSL packages
- Custom CSL's

How does it work?

This tool works in four steps.

- First it makes a backup of the existing object files.
- Then it deletes the xpmp2 copies, Livetraffic made. Not doing this led to a strange behavior because LiveTraffic uses those files to correct some other shortcomings of older aircraft objects. It therefore is a kind of cacheing preventing my changes to be seen.
- Then it reads the original file, changes the light params and writes those to a temporary file.
- If all is ready, the temporary files get copied over the original ones.
- Done!

How long does it take to convert?

On my machine...

The SSD with X-Plane 12 on it:

INFO : Processing done, 2220 files have been processed!

INFO : It took 25.38 seconds to complete lights_updater

On an older HDD:

INFO : Processing done, 2216 files have been processed!

INFO : It took 56.75 seconds to complete lights_updater

Your millage will vary. Hardware, OS and a lot more possibilities :-)

Specials

aircrafts.json

This file contains the aircraft's by type as far as I could determine the correct type. I used the ICAO website a lot for codes unknown to me. [Search by: Aircraft Type Designators](#)

If you detect an aircraft not being converted correctly or is missing completely, you can add it in here.

light_params.json

This file contains the lightparams per aircraft category. Those are partially copied from airplanes that are XP12 compatible, partially an estimation by me. Here you can change the params for each light.

Typo's:

As English is not my mother tongue I am sure that not all is correct English :-) I did my best at least.

Those who find typo's or other errors may keep them as a free gift from me :-)

Custom CSL aircraft:

Supports now many Custom CSL aircraft. Some still are bad guys who misbehave :-)

I did some tests. Not all were successful.

Sometimes the xsb_aircraft.txt is not correct filled with the aircraft data (case-sensitive filenames for those with a Microso.. mindset) or aircraft are completely missing. So some will work, some don't. Try if you dare :-) The rate of success could be higher on Windows.

As long as the xsb_aircraft.txt is correct.

License

Just for the completeness:

Copyright © 2025 Richard J. M. Muller / Froggi

This program is free software: you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation, either version 3 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program. If not, see <<https://www.gnu.org/licenses/>>