

blems (Ctrl+Shift+M)

PS D:\DekstopF> arp -a

```
Interface: 172.25.255.176 --- 0x6

    Internet Address      Physical Address      Type
    172.25.255.192        7e-ec-86-db-73-ca    dynamic
    172.25.255.255        ff-ff-ff-ff-ff-ff    static
    224.0.0.22            01-00-5e-00-00-16    static
    224.0.0.251           01-00-5e-00-00-fb    static
    224.0.0.252           01-00-5e-00-00-fc    static
    239.255.255.250       01-00-5e-7f-ff-fa    static
    255.255.255.255       ff-ff-ff-ff-ff-ff    static
```

● PS D:\DekstopF> hostname

SD22

⊙ PS D:\DekstopF> net diag

The syntax of this command is:

NET

```
[ ACCOUNTS | COMPUTER | CONFIG | CONTINUE | FILE | GROUP | HELP |
  HELPMMSG | LOCALGROUP | PAUSE | SESSION | SHARE | START |
  STATISTICS | STOP | TIME | USE | USER | VIEW ]
```

● PS D:\DekstopF> ipconfig

Windows IP Configuration

Ethernet adapter Ethernet:

```
Media State . . . . . : Media disconnected
Connection-specific DNS Suffix  . :
```

Wireless LAN adapter Local Area Connection* 3:

```
Media State . . . . . : Media disconnected
Connection-specific DNS Suffix  . :
```

Wireless LAN adapter Local Area Connection* 4:

```
Media State . . . . . : Media disconnected
Connection-specific DNS Suffix  . :
```

Wireless LAN adapter Wi-Fi:

```
Connection-specific DNS Suffix  . :
IPv6 Address. . . . . : 2409:4081:1cce:a8e5:2956:8341:856f:31f5
Temporary IPv6 Address. . . . . : 2409:4081:1cce:a8e5:605e:66c7:278b:a42f
Link-local IPv6 Address . . . . . : fe80::ede:5a83:df50:5366%6
IPv4 Address. . . . . : 172.25.255.176
Subnet Mask . . . . . : 255.255.255.0
Default Gateway . . . . . : fe80::7cec:86ff:fedb:73ca%6
                          172.25.255.192
```

Ethernet adapter Bluetooth Network Connection:

```
Media State . . . . . : Media disconnected
Connection-specific DNS Suffix  . :
```

○ PS D:\DekstopF> █

● PS D:\DekstopF> **ipconfig** /all

Windows IP Configuration

Host Name : SD22
Primary Dns Suffix :
Node Type : Mixed
IP Routing Enabled. : No
WINS Proxy Enabled. : No

Ethernet adapter Ethernet:

Media State : Media disconnected
Connection-specific DNS Suffix . :
Description : Realtek PCIe GbE Family Controller
Physical Address. : E8-9C-25-1C-CF-3B
DHCP Enabled. : Yes
Autoconfiguration Enabled : Yes

Wireless LAN adapter Local Area Connection* 3:

Media State : Media disconnected
Connection-specific DNS Suffix . :
Description : Microsoft Wi-Fi Direct Virtual Adapter #3
Physical Address. : CE-47-40-EB-D5-AD
DHCP Enabled. : Yes
Autoconfiguration Enabled : Yes

Wireless LAN adapter Local Area Connection* 4:

Media State : Media disconnected
Connection-specific DNS Suffix . :
Description : Microsoft Wi-Fi Direct Virtual Adapter #4
Physical Address. : CE-47-40-EB-D5-BD
DHCP Enabled. : Yes
Autoconfiguration Enabled : Yes

Wireless LAN adapter Wi-Fi:

Connection-specific DNS Suffix . :
Description : MediaTek Wi-Fi 6 MT7921 Wireless LAN Card

● PS D:\DekstopF> **ipconfig** /renew

Windows IP Configuration

No operation can be performed on Ethernet while it has its media disconnected.
No operation can be performed on Local Area Connection* 3 while it has its media disconnected.
No operation can be performed on Local Area Connection* 4 while it has its media disconnected.
No operation can be performed on Bluetooth Network Connection while it has its media disconnected.

Ethernet adapter Ethernet:

Media State : Media disconnected
Connection-specific DNS Suffix . :

Wireless LAN adapter Local Area Connection* 3:

Media State : Media disconnected
Connection-specific DNS Suffix . :

Wireless LAN adapter Local Area Connection* 4:

Media State : Media disconnected
Connection-specific DNS Suffix . :

Wireless LAN adapter Wi-Fi:

Connection-specific DNS Suffix . :
IPv6 Address. : 2409:4081:1cce:a8e5:2956:8341:856f:31f5
Temporary IPv6 Address. : 2409:4081:1cce:a8e5:605e:66c7:278b:a42f
Link-local IPv6 Address : fe80::ede:5a83:df50:5366%6
IPv4 Address. : 172.25.255.176
Subnet Mask : 255.255.255.0
Default Gateway : fe80::7cec:86ff:fedb:73ca%6
172.25.255.192

Ethernet adapter Bluetooth Network Connection:

Media State : Media disconnected
Connection-specific DNS Suffix . :

○ PS D:\DekstopF> █

```
PS D:\DekstopF> ipconfig /release
```

Windows IP Configuration

No operation can be performed on Ethernet while it has its media disconnected.
No operation can be performed on Local Area Connection* 3 while it has its media disconnected.
No operation can be performed on Local Area Connection* 4 while it has its media disconnected.
No operation can be performed on Bluetooth Network Connection while it has its media disconnected.

Ethernet adapter Ethernet:

Media State : Media disconnected
Connection-specific DNS Suffix . :

Wireless LAN adapter Local Area Connection* 3:

Media State : Media disconnected
Connection-specific DNS Suffix . :

Wireless LAN adapter Local Area Connection* 4:

Media State : Media disconnected
Connection-specific DNS Suffix . :

Wireless LAN adapter Wi-Fi:

Connection-specific DNS Suffix . :
IPv6 Address. : 2409:4081:1cce:a8e5:2956:8341:856f:31f5
Temporary IPv6 Address. : 2409:4081:1cce:a8e5:605e:66c7:278b:a42f
Link-local IPv6 Address : fe80::ede:5a83:df50:5366%6
Default Gateway : fe80::7cec:86ff:fedb:73ca%6

Ethernet adapter Bluetooth Network Connection:

Media State : Media disconnected
Connection-specific DNS Suffix . :

```
PS D:\DekstopF>
```

```
PS D:\DekstopF> ipconfig /flushdns
```

Error: unrecognized or incomplete command line.

USAGE:

```
ipconfig [/allcompartments] [/? | /all |  
/renew [adapter] | /release [adapter] |  
/renew6 [adapter] | /release6 [adapter] |  
/flushdns | /displaydns | /registerdns |  
/showclassid adapter |  
/setclassid adapter [classid] |  
/showclassid6 adapter |  
/setclassid6 adapter [classid] ]
```

where

adapter Connection name
 (wildcard characters * and ? allowed, see examples)

Options:

/?	Display this help message
/all	Display full configuration information.
/release	Release the IPv4 address for the specified adapter.
/release6	Release the IPv6 address for the specified adapter.
/renew	Renew the IPv4 address for the specified adapter.
/renew6	Renew the IPv6 address for the specified adapter.
/flushdns	Purges the DNS Resolver cache.
/registerdns	Refreshes all DHCP leases and re-registers DNS names
/displaydns	Display the contents of the DNS Resolver Cache.
/showclassid	Displays all the dhcp class IDs allowed for adapter.
/setclassid	Modifies the dhcp class id.
/showclassid6	Displays all the IPv6 DHCP class IDs allowed for adapter.
/setclassid6	Modifies the IPv6 DHCP class id.

The default is to display only the IP address, subnet mask and default gateway for each adapter bound to TCP/IP.

For Release and Renew, if no adapter name is specified, then the IP address leases for all adapters bound to TCP/IP will be released or renewed.

For Setclassid and Setclassid6, if no ClassId is specified, then the ClassId is removed.

Examples:

> ipconfig	... Show information
> ipconfig /all	... Show detailed information
> ipconfig /renew	... renew all adapters


```

PS D:\DekstopF> nslookup
Default Server: UnKnown
Address: 172.25.255.192

> ping www.google.com
Server: www.google.com
Addresses: 2001:4860:482c:7700::
           2001:4860:4828:7700::
           2001:4860:4826:7700::
           2001:4860:482a:7700::
           2001:4860:4827:7700::
           2001:4860:4829:7700::
           2001:4860:482b:7700::
           2001:4860:482d:7700::
           142.251.153.119
           142.251.155.119
           142.251.150.119
           142.251.152.119
           142.251.156.119
           142.251.157.119
           142.251.151.119
           142.251.154.119

```

```

DNS request timed out.
    timeout was 2 seconds.
DNS request timed out.
    timeout was 2 seconds.
*** Request to www.google.com timed-out
>

```

```

PS D:\DekstopF> tracert www.google.com

```

```

Tracing route to www.google.com [2001:4860:482d:7700::]
over a maximum of 30 hops:

```

```

  1      2 ms      1 ms      3 ms  2409:4081:1cce:a8e5::a4
  2      *         *         *    Request timed out.
  3     60 ms     39 ms     49 ms  2405:200:381:eeee:20::1156
  4     77 ms     49 ms     38 ms  2405:200:801:c00::17aa
  5      *         *         *    Request timed out.
  6      *         *         *    Request timed out.

```

```

PS D:\DekstopF> nbtstat -a

```

```

Displays protocol statistics and current TCP/IP connections using NBT
(NetBIOS over TCP/IP).

```

```

NBTSTAT [ [-a RemoteName] [-A IP address] [-c] [-n]
          [-r] [-R] [-RR] [-s] [-S] [interval] ]

```

```

-a (adapter status) Lists the remote machine's name table given its name
-A (Adapter status) Lists the remote machine's name table given its
                      IP address.
-c (cache)          Lists NBT's cache of remote [machine] names and their IP addresses
-n (names)          Lists local NetBIOS names.
-r (resolved)       Lists names resolved by broadcast and via WINS
-R (Reload)         Purges and reloads the remote cache name table
-S (Sessions)       Lists sessions table with the destination IP addresses
-s (sessions)       Lists sessions table converting destination IP
                      addresses to computer NETBIOS names.
-RR (ReleaseRefresh) Sends Name Release packets to WINS and then, starts Refresh

```

```

RemoteName  Remote host machine name.
IP address   Dotted decimal representation of the IP address.
interval     Redisplays selected statistics, pausing interval seconds
              between each display. Press Ctrl+C to stop redisplaying
              statistics.

```

```

PS D:\DekstopF> nbtstat

```

```

Displays protocol statistics and current TCP/IP connections using NBT
(NetBIOS over TCP/IP).

```

```

NBTSTAT [ [-a RemoteName] [-A IP address] [-c] [-n]
          [-r] [-R] [-RR] [-s] [-S] [interval] ]

```

```

-a (adapter status) Lists the remote machine's name table given its name
-A (Adapter status) Lists the remote machine's name table given its
                      IP address.
-c (cache)          Lists NBT's cache of remote [machine] names and their IP addresses
-n (names)          Lists local NetBIOS names.
-r (resolved)       Lists names resolved by broadcast and via WINS
-R (Reload)         Purges and reloads the remote cache name table
-S (Sessions)       Lists sessions table with the destination IP addresses
-s (sessions)       Lists sessions table converting destination IP
                      addresses to computer NETBIOS names.
-RR (ReleaseRefresh) Sends Name Release packets to WINS and then, starts Refresh

```

```

RemoteName  Remote host machine name.

```