

User Interface

event

cyboi	unix_terminal	win32_console	x_window_system	win32_display	java_script	java	description
inline	-	-	-	-	-	-	-
file	-	-	-	-	-	-	-
keyboard		KEY_EVENT					
mouse		MOUSE_EVENT					
-		WINDOW_BUFFER_SIZE_EVENT					
-		MENU_EVENT					
-		FOCUS_EVENT					
				WM_CAPTURECHANGED			
				WM_LBUTTONDOWNCLK			
				WM_LBUTTONDOWN			
				WM_LBUTTONUP			
				WM_MBUTTONDOWNCLK			
				WM_MBUTTONDOWN			
				WM_MBUTTONUP			
				WM_MOUSEACTIVATE			
				WM_MOUSEHOVER			
				WM_MOUSEHWHEEL			
				WM_MOUSELEAVE			
				WM_MOUSEMOVE			
				WM_MOUSEWHEEL			
				WM_NCHITTEST			
				WM_NCLBUTTONDOWNCLK			
				WM_NCLBUTTONDOWN			
				WM_NCLBUTTONUP			
				WM_NCMBUTTONDBLCLK			
				WM_NCMBUTTONDOWN			
				WM_NCMBUTTONUP			
				WM_NCMOUSEHOVER			
				WM_NCMOUSELEAVE			
				WM_NCMOUSEMOVE			
				WM_NCRBUTTONDOWNCLK			
				WM_NCRBUTTONDOWN			
				WM_NCRBUTTONUP			
				WM_NCXBUTTONDOWNCLK			
				WM_NCXBUTTONDOWN			
				WM_NCXBUTTONUP			
				WM_RBUTTONDOWNCLK			
				WM_RBUTTONDOWN			
				WM_RBUTTONUP			
				WM_XBUTTONDOWNCLK			
				WM_XBUTTONDOWN			
				WM_XBUTTONUP			
touchpad							
joystick							
scanner							
barcode_reader							
socket							

User Interface

state

cyboi	unix_terminal	win32_console	x_window_system	win32_display	java_script	java	description
key_pressed		bKeyDown is true					
key_released		bKeyDown is false					
repeat_count		wRepeatCount					indicates that a key is being held down
key_code_virtual		wVirtualKeyCode					identifies key in a device-independent manner
key_code_device		wVirtualScanCode					device-dependent value generated by the keyboard hardware
character		uChar - UnicodeChar					translated Unicode character
mask		dwControlKeyState					state of the control keys

cyboi	unix_terminal	win32_console	x_window_system	win32_display	java_script	java	description
		CAPSLock_ON 0x0080					The CAPS LOCK light is on.
		ENHANCED_KEY 0x0100					The key is enhanced.
		LEFT_ALT_PRESSED 0x0002					The left ALT key is pressed.
		LEFT_CTRL_PRESSED 0x0008					The left CTRL key is pressed.
		NUMLOCK_ON 0x0020					The NUM LOCK light is on.
		RIGHT_ALT_PRESSED 0x0001					The right ALT key is pressed.
		RIGHT_CTRL_PRESSED 0x0004					The right CTRL key is pressed.
		SCROLLLOCK_ON 0x0040					The SCROLL LOCK light is on.
		SHIFT_PRESSED 0x0010					The SHIFT key is pressed.
				MK_CONTROL 0x0008			The CTRL key is down.
				MK_LBUTTON 0x0001			The left mouse button is down.
				MK_MBUTTON 0x0010			The middle mouse button is down.
				MK_RBUTTON 0x0002			The right mouse button is down.
				MK_SHIFT 0x0004			The SHIFT key is down.
				MK_XBUTTON1 0x0020			The first X button is down.
				MK_XBUTTON2 0x0040			The second X button is down.