Lab - 18 Assigning Static IP Address

ProbLem

This tutorial will show you how to set a static IP address on your Pi with the release of Raspbian Jessie. At the time of writing, the latest release date of Raspbian Jessie is 18-03-2016 with Kernal version 4.1.

Solution


I recommend doing this on a fresh install, however if you have attempted to set a static IP address already, you may have found yourself editing the interfaces file (/etc/network/interfaces). I hope you made a backup, because you'll need to remove any edits you have made, and revert it back to its original state!

Discussion

The following is done over SSH, but you could just as well plug your Pi into a monitor, hook up a keyboard and mouse, and use the Terminal instead.

Start by editing the dhcpcd.conf file

sudo nano /etc/dhcpcd.conf



Scroll all the way to the bottom of the file and add one, or both of the following snippets. Depending on whether you want to set a static IP address for a wired connection or a wireless connection eth0 = wired, wlan0 = wireless.

You'll need to edit the numbers in the snippet so they match your network configuration.

Workshop on "Internet of Things for Real Time Applications" - CSE / REC - 34

CODE

interface eth0

static ip_address=192.168.0.10/24
static routers=192.168.0.1
static domain_name_servers=192.168.0.1
interface wlan0

static ip_address=192.168.0.200/24
static routers=192.168.0.1
static domain_name_servers=192.168.0.1

interface = This defines which network interface you are setting the configuration for.


static ip_address = This is the IP address that you want to set
your device to. (Make sure you leave the /24 at the end)

static routers = This is the IP address of your gateway (probably
the IP address or your router)

static domain_name_servers = This is the IP address of your DNS (probably the IP address of your router). You can add multiple IP addresses here separated with a single space.

To exit the editor, press ctrl+x

To save your changes press the letter "Y" then hit enter



Now all you need to do is reboot, and everything should be set! reboot

You can double check by typing

ifconfig

And checking the interfaces IP address

```
Last login: Wed Apr Z0 U): 56:08 Z016
plframpberrypi: Sudo name /etc/dhcpod.comf
plframpberrypi: Judo name /etc/dhcpod.comf
plframpberrypi: liconing
e.h0 Link emcap:Ethermet HWaddr b8:27:eb:f3:63:7e
inct6 addr: fc80::214a:1361:51f:cbd/61 Sospe:Link
UP RECADERST MLITICAST MUDISOO Matric:1
RX packets:0 errors:0 dropped:0 overrum:0 frame:0
TX packets:0 errors:0 dropped:0 overrum:0 carrier:0
collisions:0 txqueuelen:1000
RX bytes:0 (0.0 B) TX bytes:0 (0.0 B)

L0 Link encap:Local Loopback
inet addr: 1:1/128 Sospe:Host
UP LOOPBACK RINNING MIT:655.36 Metric:1
RX packets:080 errors:0 dropped:0 overrums:0 frame:0
TX packets:080 errors:0 dropped:0 overrums:0 carrier:0
collisions:0 txqueuelen:0
RX bytes:30600 (32.0 HiD) TX bytes:03600 (32.0 HiB)

VIANO
Link encap:Etherner, HWaddr d4:7h:bh:14:88:ce
inet addr:122.160.0.200 Deast:132.160.0.255 Mask:255.255.255.0
Linet6 a3dr: resu::ds/bicoff:fe14:88ce/64 Sospe:Link
UP BROADCAST RUNNING MULICAST MUDISO. Mearic:1
RX packets:390 errors:0 dropped:0 overrums:0 frame:0
TX packets:390 errors:0 dropped:0 overrums:0 carrier:0
collisions:0 txqueuelen:1000
RX bytes:290071 (203.2 HiB) TX bytes:56694 (55.3 HiB)
```