


Часть 1: Построение сети и настройка базовых параметров устройства

Создал сеть по топологии из условия задачи. Задал имена устройств.

Настроил устройства согласно таблице адресации, назначил имена всем интерфейсам.



Часть 2: Настройка и проверка маршрутизации RIPv2

Настроил маршрутизацию RIPv2 на всех маршрутизаторах в сети. Отключил автоматическое суммирование, настроил маршрут по умолчанию и проверил сквозное соединение. Настроил и перераспределили маршрут по умолчанию для получения доступа к Интернету.

IOS Command Line Interface

```
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up

Router(config-if)#exit
Router(config)#interface GigabitEthernet0/2
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to
Router(config-if)#
Router(config-if)#exit
Router(config)#interface GigabitEthernet0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface GigabitEthernet0/1
Router(config-if)#
Router(config-if)#exit
Router(config)#interface GigabitEthernet0/1
Router(config-if)#
Router(config-if)#exit
Router(config)#interface GigabitEthernet0/2
Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2, changed state to
Router(config-if)#
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip in
Router#show ip interface brief
Interface                IP-Address      OK? Method Status      Protocol
GigabitEthernet0/0       209.165.201.1   YES manual up          up
GigabitEthernet0/1       10.1.1.2        YES manual up          up
GigabitEthernet0/2       10.2.2.2        YES manual up          up
Vlan1                    unassigned      YES unset  administratively down down
Router#
```

Router 1

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#no auto-su
Router(config-router)#no auto-summary
Router(config-router)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#clear ip route *
```

Router 2

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#no auto-s
Router(config-router)#no auto-summary
Router(config-router)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#clear ip route *
```

Router 3

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>
Router>en
Router#router rip
      ^
% Invalid input detected at '^' marker.

Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#no auto-s
Router(config-router)#no auto-summary
Router(config-router)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
Router#clear ip route *
```

