





Цель работы: научиться создавать исполняемые (*.bat) файлы для диагностики работы ЛВС.

Выполнение заданий:


Вариант 11

Bat





OSPF



```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int gi0/0
Router(config-if)#ip address 10.10.10.1 255.255.255.252
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#int gi0/1
Router(config-if)#ip address 10.10.11.1 255.255.255.252
Router(config-if)#exit
Router(config)#int gi0/2
Router(config-if)#ip address 192.168.1.1 255.255.255.0
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2, changed state to up

Router(config-if)#exit
Router(config)#int gi0/1
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up

Router(config-if)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#wr mem
Building configuration...
[OK]
Router#
```


would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>en

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#int gi0/0

Router(config-if)#ip address 10.10.10.2 255.255.255.252

Router(config-if)#no sh

Router(config-if)#

%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up

Router(config-if)#exit

Router(config)#int gi0/1

Router(config-if)#ip address 10.10.12.1 255.255.255.252

Router(config-if)#no sh

Router(config-if)#

%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up

Router(config-if)#exit

Router(config)#int gi0/2

Router(config-if)#ip address 192.168.2.1 255.255.255.0

Router(config-if)#no sh

Router(config-if)#


%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2, changed state to up

Router(config-if)#exit

Router(config)#

☐ Top



```
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int lo0
Router(config)#int loopback 0

Router(config-if)#
%LINK-5-CHANGED: Interface Loopback0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up

Router(config-if)#ip address 192.168.100.1 255.255.255.255
Router(config-if)#no sh
Router(config-if)#exit
Router(config)#router ospf 1
Router(config-router)#network 192.168.1.0 0.0.0.255 area 0
Router(config-router)#network 10.10.10.0 0.0.0.3 area 0
Router(config-router)#network 10.10.11.0 0.0.0.3 area 0
Router(config-router)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#wr mem
Building configuration...
[OK]
Router#
```

☐ Top



```
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int gi0/0
Router(config-if)#ip address 10.10.12.2 255.255.255.252
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#int gi0/1
Router(config-if)#ip address 10.10.11.2 255.255.255.252
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up


Router(config-if)#exit
Router(config)#int gi0/2
Router(config-if)#ip address 192.168.3.1 255.255.255.0
Router(config-if)#no sh

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2, changed state to up

Router(config-if)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#wr mem
Building configuration...
[OK]
Router#
```

☐ Top

```
Router(config-if)#exit
Router(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up

Router(config)#int loo
Router(config)#int loopback 0

Router(config-if)#
%LINK-5-CHANGED: Interface Loopback0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up

Router(config-if)#ip address 192.168.100.2 255.255.255.255
Router(config-if)#no sh
Router(config-if)#exit
Router(config)#router ospf 1
Router(config-router)#network 192.168.2.0 0.0.0.255 area 0
Router(config-router)#network 10.10.10.0 0.0.0.3 area 0
Router(config-router)#network 10.10.12.0 0.0.0.3 area 0
00:19:38: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.100.1 on GigabitEthernet0/0 from LOADING to FULL, Loading Done

Router(config-router)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#wr mem
Building configuration...
[OK]
Router#
```

☐ Top

```
[OK]
Router#
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int loo
Router(config)#int loopback 0

Router(config-if)#
%LINK-5-CHANGED: Interface Loopback0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up

Router(config-if)#ip address 192.168.100.3 255.255.255.255
Router(config-if)#no sh
Router(config-if)#exit
Router(config)#router ospf 1
Router(config-router)#network 192.168.3.0 0.0.0.255 area 0
Router(config-router)#network 10.10.11.0 0.0.0.3 area 0
Router(config-router)#network 10.10.12.0 0.0.0.3 area 0
Router(config-router)#en
% Ambiguous command: "en"
Router(config)#
00:23:02: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.100.1 on GigabitEthernet0/1 from LOADING to FULL, Loading Done
00:23:07: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.100.2 on GigabitEthernet0/0 from LOADING to FULL, Loading Done

Router(config)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#wr mem
Building configuration...
[OK]
Router#
```

☐ Top

[OK]

Router#

Router#show ip ospf neighbor

Neighbor ID	Pri	State	Dead Time	Address	Interface
192.168.100.2	1	FULL/DR	00:00:33	10.10.12.1	GigabitEthernet0/0
192.168.100.1	1	FULL/DR	00:00:38	10.10.11.1	GigabitEthernet0/1

Router#

☐ Top



Command Prompt

Cisco Packet Tracer PC Command Line 1.0

C:\>ping 192.168.2.2

Pinging 192.168.2.2 with 32 bytes of data:

Request timed out.

Reply from 192.168.2.2: bytes=32 time<1ms TTL=126

Reply from 192.168.2.2: bytes=32 time<1ms TTL=126

Reply from 192.168.2.2: bytes=32 time<1ms TTL=126

Ping statistics for 192.168.2.2:

Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>ping 192.168.1.2

Pinging 192.168.1.2 with 32 bytes of data:

Request timed out.

Reply from 192.168.1.2: bytes=32 time<1ms TTL=126

Reply from 192.168.1.2: bytes=32 time=1ms TTL=126

Reply from 192.168.1.2: bytes=32 time<1ms TTL=126

Ping statistics for 192.168.1.2:

Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 1ms, Average = 0ms


C:\>|

☐ Top

Copper Cross-Over

Toggle PD






```
Router>show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route


Gateway of last resort is not set

10.0.0.0/8 is variably subnetted, 5 subnets, 2 masks
C       10.10.10.0/30 is directly connected, GigabitEthernet0/0
L       10.10.10.1/32 is directly connected, GigabitEthernet0/0
C       10.10.11.0/30 is directly connected, GigabitEthernet0/1
L       10.10.11.1/32 is directly connected, GigabitEthernet0/1
O       10.10.12.0/30 [110/2] via 10.10.10.2, 00:03:21, GigabitEthernet0/0
        [110/2] via 10.10.11.2, 00:03:21, GigabitEthernet0/1
192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.1.0/24 is directly connected, GigabitEthernet0/2
L       192.168.1.1/32 is directly connected, GigabitEthernet0/2
O       192.168.2.0/24 [110/2] via 10.10.10.2, 00:06:52, GigabitEthernet0/0
O       192.168.3.0/24 [110/2] via 10.10.11.2, 00:03:21, GigabitEthernet0/1
192.168.100.0/32 is subnetted, 1 subnets
C       192.168.100.1/32 is directly connected, Loopback0

Router>
Router>
Router>
```

☐ Top





Контрольные вопросы

1. Что такое BAT?

BAT файл является командным файлом DOS, который производит выполнение команд посредством командной строки Windows под названием "cmd.exe".

2. Для чего применяют BAT?

Использование файла BAT распространено при запуске различных программ, так же данные пакетные файлы могут быть необходимыми для контроля утилит, отвечающих за обслуживание системы Windows.

3. Что хранит в себе формат BAT?

Формат BAT хранит в себе определенные линейные команды.

Вывод: я научился создавать исполнительные (*.bat) файлы для диагностики работы ЛВС.