TABLE OF CONTENTS

Launching the Application from Command Line3	
SFTPPipeline Dashboard4	
Active Upload Widget5	
Admin Login Widget6	
Object Management:	
QtDesigner: Installation & Main Window10	
Adding UI Files to the Python Application12	
Packaging Into An Executable	
Database Schema	




SFTP Pipeline User Guide



EXTRA FUNCTIONALITY

QtDesigner | Pyuic5



QtDesigner .ui can be loaded directly by the constructor or converted to .py files using the following command, as discussed in the **pyuic5** section: pyuic5 -x example.ui -o example.py

PyQt5-tools



Contains QtDesigner. Install with: pip install pyqt5-tools
Located in your python folder:
[python folder] / Lib / site-packages / qt5_applications / Qt / bin/ designer.exe

PyInstaller



Allows packaging the SFTP tool into a single executable. Install with:

pip install pyinstaller

5

MODULE DEPENDENCIES

PyQt5



GUI framework in which the User Interface is developed. Can be used to implement new UI elements in future development.

MySQL Connector



Self-contained python driver for communicating with MySQL servers.


Hash Lib



Contains cryptographic and hashing functions that are used in the application.

LAUNCHING THE APPLICATION FROM COMMANDLINE

Open your File Explorer, and navigate to the 'application/src' directory...



Inside the '/src' directory, you see the SFTPPipeline.py file. following command: 'python SFTPPipeline.py'

Open a Terminal window in this location, and then execute the

The application window should appear.

Errors may occur in the absence of modules the application depends upon, and may be reconciled with the Note: execution of the following command:

'pip install [API/Module Name] '

SFTPPipeline Dashboard

The SFTPPipeline Dashboard initially consists of 5 main widgets:

- A. Displays user-created


 Jobs consisting of one
 or more Presets
- B. Displays user-created Presets consisting of one or more Files
- C. Displays connections to any number of SFTP servers
- D. Allows authorized users to navigate to the Administrative Login portal.
- E. Active Uploads:

 Each Job/Preset will

 display upload


 progress with respect

 to individual files.



Active Uploads Widget

Consider the Active Uploads widget below.




Deliverables can be selected in the form of **Jobs** and **Presets**.

Multiple Jobs/Presets can be selected simultaneously, and their individual files will be added to the **Active Uploads** pane.

Upon clicking **Upload**, their progress is displayed incrementally, with respect to individual files.

<u>Important Note:</u> New **Users**, **Presets**, **Jobs**, and SFTP **Connections** can only be created by authorized users who have been authenticated through the **Admin Login** widget, as depicted in the following section.




Users Presets Jobs Connections Users List New User Alex Jordan Gabriel Yoshi Blaine Steven Password Add User

The **Users List** allows Admins to add and delete Users from the database.

In this example, this affects
Users' ability to use the
Administrative widgets

Object Management: Presets List

The Presets List has a considerably more intricate interface.



Presets can be effortlessly deleted by selecting one or more Presets in the Presets pane (A) followed by clicking the button Delete Selected Preset. (C)

- (A) Existing **Presets** can be selected in this window, causing the associating files to populate the **Files List** (B).
- New Presets can be created by clicking the File Selector window opens a new window. users can then select multiple files to add to the Files List.
- (E) After doing so, one or more Servers (E) can be selected, designating them to the **Preset**. Click a server a 2nd time if you wish to deselect it and disassociate it from the **Preset** you are creating.
- (F) Lastly, a **Preset Name** must be provided in the insertion field, and the **Add Preset** button clicked in order for the new **Preset** to be created.

Object Management: Connections List Connections Users Presets Jobs Users can create new **Connections** from this window, by **SFTP Connections New Connection** providing the following, and then clicking Add Connection Remote Directory Server • A Server Name sftp 1 sftp.alexpro.net • A Username Username • A Password • A valid URL for the Remote Directory. Password Connections can be removed by selecting them in the list Remote Directory and then clicking Delete Selected Connection(s). Delete Selected Connection(s) Add Connection

QtDesigner: Installation

The first step is installing QtDesigner. Open a Command Prompt and execute the command

pip install pyqt5-tools

You can find your python folder by executing the command:


python -c "import sys; print(sys.path)"

Then navigating to the folder:

... / [Pythonxxx] / Lib / site-packages / qt5_applications / Qt / bin/ designer.exe

Right-click your executable and Pin To Start, Pin to Taskbar, or Create [a] Shortcut to save yourself time in the future.

Launch the application.



[This does not require a visual demonstration.]

QtDesigner: Main Window

The main window should open with a smaller, **New**Form window displayed on top of it. The primary two elements you will likely be concerned with are of course Main Window and Widget. You will first want to create a Main Window.

Note: Keep the **Device** and **Screen Size** properties in mind when designing UI windows and widgets, as they may impact performance on a diverse variety of machines.


□ Push Button
□ Tool Button
□ Redio Button
□ Check Box
□ Check Box

QtDesigner's visibility may depend on your device's resolution. The new **MainWindow** will appear in the middle pane.

From here, you can insert **Buttons**, **Labels**, **Widgets**, and a myriad of other objects to your Main Window from your **Widget Box** (left). Any object created can be selected via the **Object Inspector** (top right), and its properties viewed and edited in the **Property Editor** further down.

For a more in-depth tutorial on QtDesigner creating complex graphical user interfaces, consider watching the PyQt5 QtDesigner tutorial linked below:

https://www.youtube.com/playlist?list=PLzMcBGfZo4-IB8MZfHPLTEHO9zJDDLpYj



QtDesigner: PYUIC5

~/SFTPPipeline/src/views/MainWindow.py

```
24 ∨ class MainWindow(QtWidgets.QMainWindow):
         # Function: Constructor
         # Parameters: None
         # Return: MainWindow UI object
         def init (self):
             # Call OMainWindow Constructor
             super(MainWindow, self). init ()
             uic.loadUi(r"./views/MainWindow.ui", self)
34
             # Initialize User
             self.User = User()
             # Initialize Security Object
             self.Security = Security()
             # Load Widgets
             self.Admin Button = self.findChild(OtWidgets.QLabel, "Admin Button")
             self.Stacked_Widget = self.findChild(QtWidgets.QStackedWidget, "stackedWidget")
C:\SFTPPipeline\src\practice_example\views>dir
 Volume in drive C is Win11 Pro
 Volume Serial Number is 1E60-8E18
Directory of C:\SFTPPipeline\src\practice_example\views
04/05/2023 08:34 PM
                         <DIR>
04/05/2023 08:34 PM
                         <DIR>
04/05/2023 08:36 PM
                                 36,273 MainWindow.py
03/27/2023 05:18 PM
                                 40,108 MainWindow.ui
02/13/2023 04:22 PM
                                 11,330 MainWindow_OLD.py
04/05/2023 08:34 PM
                         <DIR>
                                         __pycache__
               3 File(s)
                                  87,711 bytes
               3 Dir(s) 701,989,183,488 bytes free
C:\SFTPPipeline\src\practice_example\views>pyuic5 -x MainWindow.ui -o MainWindow.py
```

OPTIONAL FEATURES

As mentioned on pg. 2, line 33 of our code demonstrates the python constructor of our code incorporates .ui files into the application directly.


However, the API **pyuic5** can optionally convert .ui files to .py files which can then be used as **Views** in your python application.

Packaging Into An Executable

You can install PyInstaller with: pip install pyinstaller"

```
:\SFTPPipeline\src>pip install pyinstaller
Collecting pyinstaller
 Downloading pyinstaller-5.10.1-py3-none-win_amd64.whl (1.3 MB)
Requirement already satisfied: setuptools>=42.0.0 in c:\users\steve\appdata\local\programs\python\python310\lib\site-packages (from pyinst
aller) (65.5.0)
Collecting altgraph
 Downloading altgraph-0.17.3-py2.py3-none-any.whl (21 kB)
Collecting pywin32-ctypes>=0.2.0
 Downloading pywin32_ctypes-0.2.0-py2.py3-none-any.whl (28 kB)
Collecting pefile>=2022.5.30
 Downloading pefile-2023.2.7-py3-none-any.whl (71 kB)
                                              71.8/71.8 kB ? eta 0:00:00
Collecting pyinstaller-hooks-contrib>=2021.4
 Downloading pyinstaller_hooks_contrib-2023.2-py2.py3-none-any.whl (261 kB)
Installing collected packages: pywin32-ctypes, altgraph, pyinstaller-hooks-contrib, pefile, pyinstaller
Successfully installed altgraph-0.17.3 pefile-2023.2.7 pyinstaller-5.10.1 pyinstaller-hooks-contrib-2023.2 pywin32-ctypes-0.2.0
```

Then, navigate to your '~/SFTPPipeline/src ' folder:



Execute the following command:


pyinstaller --add-data "views; views" --add-data "assets; assets" --onefile SFTPPipeline.py

A very intimidating wall of output should flood your command line.

```
C:\Windows\System32\cmd.e X
C:\SFTPPipeline\src>pyinstaller --add-data "views;views" --add-data "assets;assets" --onefile SFTPPipeline.py
693 INFO: PyInstaller: 5.10.1
693 INFO: Python: 3.10.10
705 INFO: Platform: Windows-10-10.0.22621-SP0
707 INFO: wrote C:\SFTPPipeline\src\SFTPPipeline.spec
711 INFO: UPX is not available.
718 INFO: Extending PYTHONPATH with paths
['C:\\SFTPPipeline\\src']
1167 INFO: Appending 'datas' from .spec
1171 INFO: checking Analysis
1184 INFO: Building because inputs changed
1184 INFO: Initializing module dependency graph...
1187 INFO: Caching module graph hooks...
1220 INFO: Analyzing base_library.zip ...
3516 INFO: Loading module hook 'hook-encodings.py' from 'C:\\Users\\steve\\AppData\\Local\\Programs\\Python\\R
kages\\PyInstaller\\hooks'...
5664 INFO: Loading module hook 'hook-pickle.py' from 'C:\\Users\\steve\\AppData\\Local\\Programs\\Python\\Pyth
es\\PyInstaller\\hooks'...
6828 INFO: Loading module hook 'hook-heapq.py' from 'C:\\Users\\steve\\AppData\\Local\\Programs\\Python\\Pytho
s\\PyInstaller\\hooks'...
8546 INFO: Caching module dependency graph...
8689 INFO: running Analysis Analysis-00.toc
8730 INFO: Adding Microsoft. Windows. Common-Controls to dependent assemblies of final executable
 required by C:\Users\steve\AppData\Local\Programs\Python\Python310\python.exe
9391 INFO: Analyzing C:\SFTPPipeline\src\SFTPPipeline.py
9418 INFO: Loading module hook 'hook-PyOt5.py' from 'C:\\Users\\steve\\AppData\\Local\\Programs\\Python\\Pytho
s\\PyInstaller\\hooks'...
9691 INFO: Loading module hook 'hook-PyOt5.uic.py' from 'C:\\Users\\steve\\AppData\\Local\\Programs\\Python\\F
kages\\PyInstaller\\hooks'...
9949 INFO: Processing pre-find module path hook PyQt5.uic.port_v2 from 'C:\\Users\\steve\\AppData\\Local\\Prog
\\lib\\site-packages\\PyInstaller\\hooks\\pre_find_module_path\\hook-PyOt5.uic.port_v2.py'.
```


Note:

Pyinstaller will produce the folder and executable depicted below. Ignore the external executable. The SFTPPipeline folder contains all the assets, as well as the EXE it needs.



Database Schema

You can see several folders and files in this directory, including the SFTPPipeline.exe file that will launch this program. This 'SFTPPipeline' folder is self-containing. It can be moved out of the '/src/dist' folder, and into another location, such as moving it to the C drive, such that its location would become 'C:\Program Files\SFTPPipeline'.



Note that this executable successfully launches the application's main page so long as the user has a working connection to their company's database. For the sake of this example, the tool is connecting to a MySQL database for testing purposes.

Database Schema

