

LLARS - Getting Started & Script Setup Guide

Current User Guide

Welcome to LLARS.

LLARS stands for Local Library of Automated Routines & Scripts.

LLARS is designed so most users can set up and run scripts through the GUI without editing the .ahk file. This guide focuses on choosing a script, configuring the values it needs, understanding RunCount/Timer behavior, and knowing what LLARS will do while a run is active.

Table of Contents

1. Before You Start
2. Choosing and Launching a Script
3. How LLARS Configuration Is Split
4. The Main Setup Tools
5. Configuration Status and Reset Config
6. Setting Up Coordinates
7. Setting Up Hotkeys
8. Setting Up Colors
9. Optional Settings and Dependencies
10. RunCount vs Timer Scripts
11. Starting a Run
12. What Happens to RuneScape Focus
13. Pausing, Resuming, and Stopping
14. Random Sleep
15. Developer Mode
16. If You Change Your Game Layout
17. Common Problems
18. Best Practices
19. About LLARS
20. The Simple Version

1. Before You Start

- Keep the complete LLARS folder extracted.
- Install AutoHotkey v1.1.37.02.
- Open RuneScape and arrange the game window/interface the way you plan to use it.
- Keep scripts and their Config.ini files in the LLARS folder structure.
- Read the comments in a script Config.ini the first time you set that script up.

Most users should not manually edit framework code or move individual scripts out of the project.

2. Choosing and Launching a Script

Use Script Selector.ahk when you want the project menu for choosing a script. A script can also be run directly from its folder when needed.

Each script is built for one activity and may ask for different setup. Do not assume settings from one script apply to another.

- Choose the script/activity.
- Read its Information text and Config.ini comments.
- Open the LLARS setup tools and configure only the settings that script requires.
- Start with a short test run before using a long duration or large run count.

3. How LLARS Configuration Is Split

LLARS Config.ini

The root LLARS Config.ini stores framework-wide settings such as LLARS control hotkeys, transparency, Random Sleep, and other shared options.

Script Config.ini

Every runnable script has its own Config.ini in the same folder. It describes that script's coordinates, hotkeys, colors, sleep/timer ranges, optional features, and any script-specific settings.

Note: Use the GUI for normal colors/coordinates/hotkeys setup. Config.ini is still worth reading because comments often explain exactly what to select or how an activity must be arranged.

4. The Main Setup Tools

Information

Shows script-specific information and is the first place to check when you are unsure how an activity is intended to work.

Colors / Coordinates / Hotkeys

This is the main script-specific setup area. LLARS shows only typed settings that exist in the current script.

Configuration Status

Shows whether typed settings are Ready, Missing, or Not Required.

Reset Config

Clears selected typed colors/coordinates/hotkeys without changing unrelated script settings.

5. Configuration Status and Reset Config

Status	Meaning
Ready	The required typed value is configured.
Missing	The script still needs this setting before it can run correctly.
Not Required	The setting is currently disabled or depends on a disabled feature.

Reset Selected clears the chosen typed value. Clear All clears typed hotkey/coordinate/color values in the current script after confirmation. Sleep ranges, timer values, option flags, unrelated settings, and the shared LLARS Config.ini are not part of script Reset Config.

6. Setting Up Coordinates

Coordinate settings tell a script where something is inside the RuneScape client.

Coordinate area

Many actions use a rectangular area rather than one exact pixel. Follow the script comment and drag/select the requested region. LLARS can choose a randomized point inside that range when the script clicks.

Exact pixel

Color-detection scripts usually use one exact Pixel Coordinate. Select the exact point requested by the script instructions.

- Set up RuneScape first, then capture coordinates.
- Do not move/rescale important interface elements afterward unless you plan to capture them again.
- Read the comment above each Config.ini coordinate section; different sections may want different kinds of selections.

7. Setting Up Hotkeys

Configured hotkeys are user-selectable RuneScape bindings. Make sure the chosen key actually performs the intended action in RuneScape before saving it in LLARS.

1. Open Colors/Coordinates/Hotkeys.
2. Choose Hotkeys.
3. Select the script setting.
4. Enter the desired key or combination.
5. Save and test it in RuneScape.

Note: Some scripts also use purposeful fixed keys such as Space or Enter. Those do not appear as configurable script hotkeys because the script is designed to use that key directly.

8. Setting Up Colors

Color settings let a script recognize a particular game state at a configured pixel.

6. Open the relevant RuneScape state so the desired color is visible.

7. Open Colors/Coordinates/Hotkeys and choose Colors.
8. Select the target color setting.
9. Follow LLARS instructions to capture the color.
10. Save the value.

Multi-color scripts can have several Target Color sections for one Pixel Coordinate. Each color represents a valid state the script knows how to recognize.

9. Optional Settings and Dependencies

Some script features can be disabled. When an optional parent feature is off, its dependent coordinate/hotkey/color settings normally show Not Required instead of Missing.

Only enable and configure optional behavior you actually intend to use. This keeps Configuration Status focused on the setup that matters for the run.

10. RunCount vs Timer Scripts

RunCount

A RunCount script asks how many complete repetitions to perform. Enter a whole number from 1 to 1000. One run means one complete sequence as defined by that script.

Timer

A Timer/MultiTimer/Color script asks how long to run in minutes. Decimals are accepted: 0.5 = 30 seconds, 1 = 1 minute, 10 = 10 minutes.

Use a small value for the first test so you can confirm the script setup before a longer session.

11. Starting a Run

When Start is pressed, LLARS validates required configuration, prompts for the RunCount or duration, captures the RuneScape client for the run, and changes the GUI into the running state.

RunCount estimate

Before loop 1 starts, LLARS calculates a starting loop/run estimate from the script's standardized timing configuration. The estimate is shown before automation begins and becomes more accurate as following loops complete. During the script's true final sleep, the current-loop countdown becomes exact.

Timer countdown

Timed scripts show the user-selected remaining time. Developer Mode Progress, when open, mirrors the same live countdown.

12. What Happens to RuneScape Focus

LLARS locks the run to the exact RuneScape window selected at start. Game-facing actions such as clicks, mouse movement, keyboard input, managed timer actions, and framework pixel reads verify that RuneScape is foreground before they operate.

During waits

LLARS sleeps do not hold RuneScape in the foreground. You can Alt-Tab to another application during a long wait.

When the next action is due

LLARS brings the selected RuneScape client back to the foreground and continues only after it verifies the correct window. This prevents scripted input from being sent into the application you were using during the wait.

Important: If you do not want LLARS to take RuneScape focus when the next action becomes due, Pause the run first. Pause/Exit are the controls that stop active automation focus reclaim.

13. Pausing, Resuming, and Stopping

Pause

Pause stops the active automation state and prevents action-time focus reclaim while paused.

Resume

Resume returns the script to its running state. The next game-facing action will make sure the selected RuneScape client is foreground.

Exit

Exit ends LLARS and stops managed script timers. Use Exit if you are finished rather than leaving a paused automation running indefinitely.

14. Random Sleep

Random Sleep is a shared optional LLARS setting. When enabled, scripts that call it may occasionally wait for a random amount of time based on the configured chance and duration range.

During Random Sleep, the main GUI shows the temporary countdown. RuneScape is not forced to stay foreground during the wait. The next game-facing action restores it when needed.

15. Developer Mode

Developer Mode is primarily for script creators and troubleshooting, but advanced users can open it to see what LLARS is doing.

Full mode

- State / Run Type / Progress, then Elapsed / Final Sleep.
- Live Inspector with mouse position, Mouse RGB, and configured pixel current-vs-target colors.
- Active Hotkeys.
- Configuration Diagnostics.
- Recent Framework Actions.

Lightweight mode

Lightweight Mode uses the same window width but shows only Recent Framework Actions. The Developer Mode hotkey toggles whichever view is selected.

Coordinate overlay

While either Developer Mode view is open, LLARS temporarily draws the coordinate range for the specific NaturalClick/mouse-to-click action currently happening. The overlay disappears after the click finishes.

Developer Mode is optional. Scripts must work normally with the window closed.

16. If You Change Your Game Layout

Coordinates and pixel colors depend on the RuneScape layout you configured. If you move, resize, scale, or rearrange important game/interface elements, captured values may no longer describe the intended location/state.

- Re-capture affected coordinates.
- Re-capture colors if visual state/pixel placement changed.
- Re-test configured hotkeys if the skillbar/action binding changed.
- Use Configuration Status after resetting/reconfiguring typed values.

17. Common Problems

Configuration Error / Missing

Open Configuration Status and complete the typed settings marked Missing. Read the Config.ini comments for exactly what each section expects.

RuneScape Not Found

Make sure RuneScape is running and recognizable before starting the script.

Script clicks the wrong place

Re-check the coordinate instructions and capture the area again using the current game layout.

Pixel script does not trigger

Use Developer Mode Live Inspector to compare Current Pixel to Pixel Target for each configured color.

Developer Mode hotkey seems to open the wrong view

The hotkey remembers Full vs Lightweight. Use the Full Mode button inside Lightweight to switch the preference back to Full.

18. Best Practices

- Read the script Information and Config.ini comments before first use.
- Configure only the options you need.
- Test with a short run first.
- Use Pause before doing something that should not be interrupted by LLARS reclaiming RuneScape.
- Do not manually edit coordinates/hotkeys/colors when the GUI can configure them.
- Re-run setup after major RuneScape layout changes.
- Use Developer Mode as a troubleshooting view, not as a requirement for normal operation.

19. About LLARS

LLARS stands for Local Library of Automated Routines & Scripts. The project, framework, scripts, templates, and documentation are created and maintained by Gubna. LLARS is free and open source.

GitHub: <https://github.com/Gubna-Tech/RuneScape>

20. The Simple Version

- Open RuneScape and set up the interface for the script.
- Choose the script and read its Information/Config.ini comments.
- Use Colors/Coordinates/Hotkeys plus Configuration Status to finish setup.
- Start with a short RunCount or Timer test.
- You can Alt-Tab during waits; the next action will bring the selected RuneScape window back unless the run is paused.
- Pause when you do not want automation to reclaim RuneScape.
- Use Developer Mode only when you want extra diagnostics.
- Reconfigure coordinates/colors after changing the game layout.