

```
class rich.table.Table(*headers, title=None, caption=None, width=None, min_width=None, box=Box(...),  
    safe_box=None, padding=(0, 1), collapse_padding=False, pad_edge=True,  
    expand=False, show_header=True, show_footer=False, show_edge=True,  
    show_lines=False, leading=0, style='none', row_styles=None,  
    header_style='table.header', footer_style='table.footer', border_style=None,  
    title_style=None, caption_style=None, title_justify='center', caption_justify='center',  
    highlight=False)
```

A console renderable to draw a table.

#### Parameters

- **\*headers** (*Union[Column, str]*) – Column headers, either as a string, or *Column* instance.
- **title** (*Union[str, Text]*, *optional*) – The title of the table rendered at the top. Defaults to None.
- **caption** (*Union[str, Text]*, *optional*) – The table caption rendered below. Defaults to None.
- **width** (*int*, *optional*) – The width in characters of the table, or *None* to automatically fit. Defaults to None.
- **min\_width** (*Optional[int]*, *optional*) – The minimum width of the table, or *None* for no minimum. Defaults to None.
- **box** (*box.Box*, *optional*) – One of the constants in *box.py* used to draw the edges (see *Box*), or *None* for no box lines. Defaults to *box.HEAVY\_HEAD*.
- **safe\_box** (*Optional[bool]*, *optional*) – Disable box characters that don't display on windows legacy terminal with *raster* fonts. Defaults to True.
- **padding** (*PaddingDimensions*, *optional*) – Padding for cells (top, right, bottom, left). Defaults to (0, 1).
- **collapse\_padding** (*bool*, *optional*) – Enable collapsing of padding around cells. Defaults to False.
- **pad\_edge** (*bool*, *optional*) – Enable padding of edge cells. Defaults to True.
- **expand** (*bool*, *optional*) – Expand the table to fit the available space if True, otherwise the table width will be auto-calculated. Defaults to False.
- **show\_header** (*bool*, *optional*) – Show a header row. Defaults to True.
- **show\_footer** (*bool*, *optional*) – Show a footer row. Defaults to False.
- **show\_edge** (*bool*, *optional*) – Draw a box around the outside of the table. Defaults to True.
- **show\_lines** (*bool*, *optional*) – Draw lines between every row. Defaults to False.
- **leading** (*int*, *optional*) – Number of blank lines between rows (precludes *show\_lines*). Defaults to 0.
- **style** (*Union[str, Style]*, *optional*) – Default style for the table. Defaults to “none”.
- **row\_styles** (*List[Union[str, Style]*, *optional*) – Optional list of row styles, if more than one style is given then the styles will alternate. Defaults to None.
- **header\_style** (*Union[str, Style]*, *optional*) – Style of the header. Defaults to “table.header”.