



CONFIGURATION MANAGEMENT

Configuration Management & Secure Baseline

Documents baseline configurations for subprocessor platforms, founder laptops, and the WeCon box. No CIS benchmarking or drift scanning.

This standard documents the secure baseline configuration for each class of Masar Zero asset. Subprocessor platforms follow vendor hardening guides. Founder laptops use built-in disk encryption and OS auto-update. The WeCon box follows vendor guidance. Masar Zero does not operate CIS benchmarking or automated drift detection.

PREPARED BY	Masar Zero W.L.L.
DOCUMENT ID	MZ-POL-010
VERSION	v1.0
EFFECTIVE	12 July 2026
CLASSIFICATION	Internal Use — Authorized Recipients Only

Document Control

Document ID	MZ-POL-010	Version	v1.0
Effective Date	12 July 2026	Review Cycle	Annual (next review: July 2027)
Document Owner	Hari Krishna	Classification	Internal Use
Publisher	Masar Zero W.L.L.	Contact	hari@masarzero.com

Revision History

Version	Date	Author	Summary of Change
v1.0	12 July 2026	Masar Zero	Initial release of Configuration Management & Secure Baseline Standard.

Approval

This document is prepared by Hari Krishna and approved by Dr. A. Latif Alkhaja, Chairman of Masar Zero W.L.L. It is effective as of the date shown above and is reviewed annually or upon significant change per MZ-POL-001 §7. Distribution is restricted to authorized recipients; redistribution requires written approval from Masar Zero leadership.

Role	Name	Signature	Date
Prepared by	Hari Krishna		
Approved by	Dr. A. Latif Alkhaja (Chairman)		

1. Purpose & Scope

This standard defines the secure baseline configurations Masar Zero W.L.L. applies to its technology assets. It is the authoritative reference for "what does a properly-configured Masar Zero asset look like?" Configuration drift from these baselines is treated as a finding to be corrected.

The standard covers: (a) the WeCon V-Net box at customer stations; (b) the Masar Zero cloud resources on Vercel, Supabase, and WorkOS; (c) Masar Zero founder laptops. Each section below documents the baseline and the responsible party.

2. WeCon V-Net Box Baseline

The WeCon V-Net box is the industrial controller inside the VRU machine cabinet. Its baseline is derived from the WeCon industrial security application guide. Key baseline elements:

- Engineering access password-protected; runtime mode protected.
- Communication via Modbus RTU/TCP over serial or Ethernet; no internet protocols enabled on the box.
- Engineering access (WeCon V-Net Designer / ladder programming port) disabled except during scheduled maintenance.
- HMI screen-saver password + USB-port disablement.
- Firmware: latest stable WeCon firmware, applied within 30 days of advisory.
- Physical tamper: WeCon box and HMI are in a locked cabinet.

Configuration changes are made only by founders, either from the local HMI at the station or via the WeCon cloud console. Founders document configuration changes in a Google Sheet.

3. Cloud Platform Baselines

Masar Zero cloud resources on Vercel, Supabase, and WorkOS follow vendor hardening guides plus Masar Zero-specific configurations.

3.1 Vercel

- Deployment protection enabled for preview deployments (Vercel Access token required).
- HSTS, X-Frame-Options, X-Content-Type-Options, Referrer-Policy headers set in next.config.js.
- Environment variables: production secrets never in preview or development environments.
- DDoS protection: Always-On (Vercel platform default).

3.2 Supabase

- Row-level security enabled on all tables; no table is exempt.
- Service-role key used only by Vercel serverless functions; never exposed to client.
- anon key has read-only access to a minimal set of public tables.
- Daily automated backups enabled (Supabase platform default).

- Network restrictions: PostgREST only; no direct Postgres access from internet.

3.3 WorkOS

- MFA: TOTP mandatory for all users.
- Password policy: per WorkOS defaults (min length, complexity, breach check).
- Session lifetime: per WorkOS defaults.
- SSO: Google Workspace available for founder accounts.
- Audit log: enabled; daily export via WorkOS admin API.

4. Founder Laptop Baseline

Masar Zero founder laptops (macOS or Windows) follow a minimal baseline:

- Disk encryption enabled (FileVault on macOS, BitLocker on Windows).
- OS auto-update enabled (security updates installed within 72 hours of release).
- Browser auto-update enabled.
- Screen lock after 15 minutes idle; password required to unlock.
- Built-in firewall enabled (macOS Application Firewall / Windows Defender Firewall) with default settings.
- Built-in anti-malware enabled (macOS XProtect / Windows Defender).
- No local admin account for daily use; admin account separate with strong password.
- 1Password installed for credential management.

Masar Zero does not operate MDM (Jamf or Intune). Founder laptops are personally managed but must meet the baseline above. Founders self-attest compliance annually.

5. Configuration Drift Detection

Masar Zero does not operate automated configuration drift detection (no OpenSCAP, no CIS benchmark scanning). Configuration drift is detected through: (a) founder observation during routine work; (b) subprocessor dashboard review (Vercel, Supabase, WorkOS); (c) annual self-attestation by founders that baselines are still in place. Any drift detected is corrected within 5 business days.

6. Change Management

All configuration changes — whether to fix drift or to deliberately update the baseline — follow a lightweight change process: (a) founder who wants the change discusses it with the other founders; (b) change is applied; (c) founder documents the change in a Google Sheet; (d) baseline standard updated if the change is permanent.

There is no formal change ticket system. Emergency changes (e.g., responding to a P1 incident) can be made without prior discussion but must be retroactively documented within 5 business days.

7. References

- MZ-POL-001 — Governance Program
- MZ-POL-005 — Vulnerability & Patch Management
- WeCon V-Net Series — Industrial Security Application Guide
- Vercel Security — <https://vercel.com/security>
- Supabase Security — <https://supabase.com/security>
- WorkOS Security — <https://workos.com/security>

MZ-POL-010 — Configuration Management & Secure Baseline Standard. End of document.