# **GUI ProjectDelete – Delete a Project**

Robin Lamacraft 2017-06-21


#### **SCOPE**

This GUI module is called from the Main Menu (GUI Interface) to delete an existing project.

#### **LOOK AND FEEL**

The screen has several parts:

- The upper right icon buttons provide the following universal features:
  - "O" enables <u>Output</u> of the Recent Projects list by sending the contents of the Recent Projects tabular display to a file or to a printer.
  - o "R" displays the Reminder content for this screen
  - "C" enables the user to create and retrieve Configurations of this screen's layout
  - o "?" displays context Help about the use of this screen
- The "Server" selection list allows selection from various servers known to this installation of HRE. On selection of a Server, the "Login" button allows the user to access that server (if the user is already logged into that server the "Login" button will be hidden). NOTE: If this is an isolated usage of HRE where project files are only used from the same computer then the server aspects of this GUI will not show any server-related elements. There can be a one user environment. If a second computer is used to access those project files over a local network then the login on either computer must invoke the shared server mode.
- The Project "Browse" button allows the user to select the project file to be deleted
- The "Summary" button opens the GUI\_ProjectSummary module to display the details of the selected project
- The "DELETE PROJECT" button initiates the deletion of the chosen project
- The "CANCEL" button forces exit without a project deletion action.



#### **ACTIONS**

The fundamental operations are:

- 1. Open the screen according to its saved screen Layout (BR PanelConfig)
- 2. Allow the user to search for a project file to be deleted
- 3. If the project file is in use, then:
  - prevent any new logins
  - warn users of that project of this action
  - raise error with this user of project use conflict.

#### **USED BY**

All HRE users.

### **DATA CONTROLLED BY THIS MODULE**

1. None.

## **REQUIRED DATA CONTROLLED BY OTHER MODULES**

1. None.

## **REQUIRED SERVICES**

- 1. GUI\_ProjectSummary
- 2. BR PanelConfig
- 3. BR File
- 4. BR\_Project.

## **APPLICATION PROGRAMMING INTERFACE (API)**

1. Single call with no parameters.

## **EVENT ACTIONS**

1. Need Details.

### **WARNING CONDITIONS**

1. Need details of the condition that raised the warning, example message and possible next steps.

### **ERROR CONDITIONS**

1. Need to record the condition that raised the error, example message and possible next steps.