# **GUI\_WINDOW OUTPUT**

**Revision history** 

2018-05-14	Robin Lamacraft	Original draft
2018-05-30	Rod Thompson	Added diagrams, maps, revised all text
2018-06-01	Don Ferguson	Minor edits, added note on printer defaults

# **WINDOW OUTPUT GUI**

This window is reached by any use of the "Output" Icon on the tool bar of another window. It provides a quick way for the user to either print what is displayed in the window or to save that content to a file for later use. The content can be printed or formatted in a standard manner for use with other applications.

GUI ELEMENT	ELEMENT TYPE	DESCRIPTION
USE		
TOP BAR	HEADING TEXT	blank or translation of "Window Output"
TOP BAR	RIGHT BUTTON	Only an "X" to "Close" the window
		equivalent of "Cancel"
LABEL	FIXED PLAIN TEXT	"Requesting Window"
CONTEXT	RETRIEVED PLAIN TEXT	The label of the window that made this request to
		output its contents
CHOICE 1	RADIO BUTTON	"Output to Printer" – when set the Output to
		Printer panel is visible. Also set on opening
CHOICE 2	RADIO BUTTON	"Output to File" – when set the Output to
		File panel is visible
Append "Output	t to Printer" or "Save to file"	" panels here

Window Output		х
Requesting Window  Output to Printer  Output to File	Window label	
Output Panel (appende	d)	
L	W OUTPUT GUI – Mockup	

# **OUTPUT TO PRINTER PANEL:**

This panel controls the settings for "Output to Printer" including default printer and page size settings, limited formats for text output.

NOTE: this panel should possibly be replaced by whatever printer options are provided by the local OS's default (or chosen) printer driver.

GUI ELEMENT USE	ELEMENT TYPE	DESCRIPTION
LABEL	FIXED PLAIN TEXT	"Select Printer"
COMMAND A	BUTTON	"Select Printer and Properties" button – uses local OS to select a printer
LABEL	RETRIEVED PLAIN TEXT	<printer name=""></printer>
LABEL	FIXED PLAIN TEXT	"Page Size"
PAGE SIZE	PLAIN TEXT VALUE	<page name="" size=""></page>
LABEL	FIXED PLAIN TEXT	"Page Orientation"
PORTTRAIT LANDSCAPE	PLAIN TEXT VALUE	<page name="" orientation=""></page>
LABEL	FIXED PLAIN TEXT	"Top Margin Height"
TOP MARGIN HEIGHT	PLAIN POSITIVE INTEGER VALUE	If empty then use default
LABEL	FIXED PLAIN TEXT	"Left Margin Width"
LEFT MARGIN WIDTH	PLAIN POSITIVE INTEGER VALUE	If empty then use default
LABEL	FIXED PLAIN TEXT	"Bottom Margin Height"
BOTTOM MARGIN HEIGHT	PLAIN POSITIVE INTEGER VALUE	If empty then use default
LABEL	FIXED PLAIN TEXT	"Right Margin Width"
RIGHT MARGIN WIDTH	PLAIN POSITIVE INTEGER VALUE	If empty then use default
HEADER TEXT	FIXED PLAIN TEXT	<first line="" of="" output=""> Omit if blank</first>
TRAILER TEXT	FIXED PLAIN TEXT	<last line="" of="" output=""> Omit if blank</last>
COMMAND A	BUTTON	"Print" button – send content to printer and close
COMMAND A	BUTTON	"Cancel" button – close without printing

Printer name	
Page Size Page	Size
Page Orientation Page	Orientation
Top Margin Height Top	Margin Height
Left Margin Width Left	Margin Width
Bottom Margin Height Bott	om Margin Height
Right Margin Width Righ	t Margin Width
Header Text	
Trailer Text	
	<del></del>
	<u> </u>

PRINTER Output Panel – Mockup

# **OUTPUT TO FILE PANEL:**

This panel controls the settings for "Output to File"

GUI ELEMENT USE	ELEMENT TYPE	DESCRIPTION
LABEL	FIXED PLAIN TEXT	"File Output"
COMMAND A	BUTTON	"Select Folder" button – uses local OS to select a folder
LABEL	RETRIEVED PLAIN TEXT	<folder path=""></folder>
LABEL	FIXED PLAIN TEXT	"Default File Name"
FILE NAME	PLAIN TEXT VALUE	<user entry=""></user>
DATE	CHECK BOX	"Append date time to file name" If checked then file name includes time/date of creation
LABEL	FIXED PLAIN TEXT	"File Output Format"
SELECTION	FIXED VERTICAL SCROLLABLE PLAIN TEXT LIST	The initial set of file output formats are:  TXT- plain text  CSV - comma separated variable  TSV - tab separated variable
COMMAND A	BUTTON	"Save" button – write and close
COMMAND A	BUTTON	"Cancel" button – close without saving

Select Folder		
Folder Path		
efault File Name		_
File Name (user entry)		
Append date time to file nam	e	
le Output Format		
File format selection		1
TXT - plain text		
CSV - comma separated variable TSV - tab separated variable	<u> </u>	

FILE Output Panel – Mockup

#### **USED BY**

All HRE users.

## **DATA CONTROLLED BY THIS MODULE**

Data chosen by user to be output to printer or file.

### **REQUIRED DATA CONTROLLED BY OTHER MODULES**

1. None.

#### **REQUIRED SERVICES**

1. Need details

## **APPLICATION PROGRAMMING INTERFACE (API)**

1. Need Details.

### **EVENT ACTIONS**

Keyboard actions

NIL

#### 2) Mouse actions

### Left key

- a. Mouse hover over slider bar, hold key down and drag slider bar up or down
- b. Mouse key tap in slide bar box cause up or down movement.
- c. Click on each button, operates the button
- d. Click on Check Box, 'selects' or 'de-selects' the defined action
- e. Click on 'un-checked' radio button, selects that button, and 'de-selects' the other.

### Right key

Action to be determined.

3) Icon actions

left mouse key click on the 'X' icon, closes the window.

4) Keyboard shortcuts

To be determined.

### WARNING CONDITIONS

1. Need details of the condition that raised the warning, example message and possible next steps.

# **ERROR CONDITIONS**

1. Need to record the condition that raised the error, example message and possible next steps.

## WINDOW INTERACTION MAP

