GUI – CONFIGURE SIZE for Multi-Column List Patterns

Revision history

2018-05-14	Robin Lamacraft	Original draft
2018-05-15	Rod Thompson	Inserted diagrams, actions

CONFIGURATION SETTINGS – CONFIGURE SIZE

GUI ELEMENT USE	ELEMENT TYPE	DESCRIPTION
TOP BAR	HEADING TEXT	blank or translation of "Configure Size"
TOP BAR	RIGHT BUTTON	Only a "X" to "Close" the window equivalent of "Cancel"
LABEL	FIXED PLAIN TEXT	<Target Window Name>
CHOICE 1	RADIO BUTTON	<Window Configuration Name> Also set on opening
CHOICE 2	RADIO BUTTON	"Default Settings" – rarely used
LABEL	FIXED PLAIN TEXT	"Window Target Data Origin Type" e.g. "Person Events Properties" –provided from the display window definition
LABEL	FIXED PLAIN TEXT	"Minimum Window Width (pixels)"
MIN WINDOW WIDTH	PLAIN POSITIVE INTEGER VALUE	If empty then use default
LABEL	FIXED PLAIN TEXT	"Default Window Width (pixels)"
DEFAULT WINDOW WIDTH	PLAIN POSITIVE INTEGER VALUE	If empty then use default
LABEL	FIXED PLAIN TEXT	"Minimum Window Height (pixels)"
MIN WINDOW HEIGHT	PLAIN POSITIVE INTEGER VALUE	If empty then use default
LABEL	FIXED PLAIN TEXT	"Default Window Height (pixels)"
DEFAULT WINDOW HEIGHT	PLAIN POSITIVE INTEGER VALUE	If empty then use default
COMMAND 1	BUTTON	"Accept" button – accepts edits and closes the window returning to the window that made the request
COMMAND 2	BUTTON	"Cancel" button – ignores edits, but if there hasvebeen some edits made, then the user will be warned that those edits will be lost, then closes the window returning to the window that made the request

CONFIGURE SIZE Window – Mockup

1) Keyboard actions
2) Mouse actions
3) Icon actions:
    a. left mouse key click on 'X' icon:
       (closes the window)
    b. left mouse key click on 'Reminder' icon:
       (opens 'Reminder' window for this 'Send to Colleague' Message display)
    c. left mouse click on 'Help ' icon:
       (opens the Help System, searches for the section on 'Send to Colleague Message').