



HAZARDMODDING

COOP MOD

FOR
MEDAL OF HONOR:
ALLIED ASSAULT

This Modification is FREE of charge and has to be presented and provided as such, at all times!

ABOUT

The HaZardModding Coop Mod: Medal of Honor, is a free open-source project developed by HaZardModding. It allows you to play the complete game cooperatively.

Experience Medal of Honor: Allied Assault with friends and play the main campaign together, bringing a whole new level of excitement to classic missions!

Cinematic cutscenes are supported.

Chrisstrahl and Criminal started the development together officially on July 2018 and version 1.0 was relased in December under the label HaZardModding.

The Modification can be played via Internet or LAN and provides 2 public servers

The source-files can be found on GitHub Game-Files

TABLE OF CONTENTS

Introduction

- About

Installation

- GOG Galaxy
- Installation
- Un-installation

Playing

- Joining a Server
- Starting a Server

Troubleshooting

- Troubleshooting Videos and Links
- Opening the Console

Links

- Related Links
- HaZardModding Links


Credits

- Copyright Notice




GOG GALAXY

- Select the list of installed games, then select **Medal of Honor: Allied Assault War Chest**.
- Click the '**Settings**' Button at the top, next to 'Play'
- Select: '**Manage Installation**' then select: '**Show folder**'
- Follow now step by step the [Installation instructions](#)



To play the Mod using GOG Galaxy you need to start the correct Executable after the Installation '**Medal of Honor – BreakThrough**'

1. Click on the '**Settings**' Button next to 'Play'.
2. Hover over '**Additional Executables**'
3. Select there '**Medal of Honor – BreakThrough**'



INSTALLATION



The HaZardModding Coop Mod is not compatible with other modifications, except Graphics/Texture Mods.

- [1] Make sure you have a clean/fresh game installation
- [2] Make sure you use the latest version, or use the GOG release.
- [3] Copy these files into the /mainttt/ folder:
 - zzzzzz_co-op_hzm_mod_mohaa.pk3
 - mom.pk3



To see and play on public Internet Servers copy moh_breakthrough.exe and replace the existing file. Start the game each time with this new moh_breakthrough.exe – *Community Master is provided by 333networks.com*

JOINING A SERVER

Join a Server from the Server List:

Start moh_breakthrough.exe, then click on Multiplayer → Join Game → Join Internet Game → Browse Internet Servers

Join a Server by IP-Address:

Start the game, then click on Multiplayer → Join Game → Join Internet Game → enter the IP-Address of the server and click on → Connect to I.P Address.

If the server is NOT using the default port 12203 enter the port too like `89.22.456.11:12204`.

Join the HaZardModding Server:

Start the game, then click on Multiplayer → Join Game → Join Internet Game → click on HZM Coop Quick Connect to join the latest official release version.



If you use GOG Galaxy follow make sure you start the [correct executable](#).

STARTING A SERVER

Start a Server from the game Menu:

Multiplayer → Start Game → then click on → HaZardModding Coop Mod, there you can select a Mission and configure the Server settings.

Server Visibility and Connectivity

Others may not be able to join your Server unless you have enabled port forwarding on your Router or any other device that handles your access to the Internet.

The typical UDP port-range for Medal of Honor: Allied Assault is 12300 to 12330, default port is 12203.

Also make sure you are allowing the moh_breakthrough.exe executable to access the Internet on the Windows Firewall!



If you start multiple instances of the game the port will shift up. Start Server first to make it will use the default port. Players can then connect without entering the port. Close all instances of the game to make the server start at the default port again.

Others may not be able to see your server in the server list unless:

- they are using the new moh_breakthrough.exe
- your server is started as dedicated
- your server can actually connect to the Internet



To test if your server can be joined, start another instance of the game, then [open the console](#), type connect then Space, then your external IP-Address like: `connect 89.22.456.11`

You need a "IPv4 IP-Address" for others to join your server.

Even if your server is not visible on the Server List, others may still be able to join by entering your external IP-Address.

Your external IP-Address should be displayed in your Router or any other device that handles your access to the Internet.



In the console of the dedicated server you can enter `status` to see if the server is working. And `net_port` to check which port the server is actually using.

CONSOLE

Before you can open the **console** you need to **enable** it in **Options** → **Advanced** → **enable** checkbox **Console**.

The **Key** to access the **console** depends on your **Keyboard Layout** and **Language**. Please try pressing these **Keys** while you are in the game: **^** , **°** , **²** , **³** , **@** , **<** , **~** or **'**

TROUBLESHOOTING / HELP / VIDEOS

These tips are from **Elite Force 2** but it is almost identical for **Medal of Honor: Allied Assault**, until we have **MOHAA** specific videos please use these for **Guidance**.

→ **After changing Video Settings or the Monitor, the game does crash.**
[GL_StartOpenGL\(\) could not load OpenGL subsystem](#)

→ **Menu never fits the screen, scaling bigger than resolution selected.**
[Scaling, Half Screen Visible](#)

→ **Mouse not showing, being slow or not responding correctly.**
[Fix no Mouse or Mouse getting Stuck.](#)

→ **How to manually set any resolution that is not provided in the menu.**
[Widescreen Custom Resolution](#)

→ **Internet Server List not working in game menu.**
[Easy Fix Multiplayer Internet Servers - Master Server](#)

→ **Freezing and Lag**
Freezing and lag on a specific Level/Map and at some areas of a Level. Caused often by a very high Framerate, which is around or above 333.

You can fix performance issues by:

- Using the violet "Set Ultra Details" button or manually setting `seta r_primitives 2`
- Activating Monitor Synchronization, in the Advanced Video Settings
- Using the console command: `seta com_maxfps 144`

UN-INSTALLATION

- Remove the files added during the [Installation](#).

RELATED LINKS

Websites, related to Medal of Honor:

- [333-Networks Discord](#)
- [Community Launcher](#)
- [Game Server Browser Fixer](#)
- [MOHAA on ModDB.com](#)
- [Mod: Remove Nazi Symbols \(for Streamers\)](#)
- [Mod: HD-Textures](#)



HAZARDMODDING LINKS

- HaZardModding Website: HaZardModding.com
- Get Support on Discord: <http://discord.HaZardModding.com>
- HaZardModding Coop Mod on [ModDB.com](#)

CREDITS

COPYRIGHT NOTICE:

- Medal of Honor and related marks are trademarks of EA-Games and their respective owners.
- Medal of Honor: Allied Assault – War Chest developed by 2015, Inc.
Electronic Arts (EA)
EA Los Angeles
TKO Software
- All other marks, trademarks and copyrights are properties of their respective owners.



Do not contact EA-Games or their affiliates, for support on the Coop Mod! All questions regarding the Coop Mod should be directed towards HaZardModding.



Document created: 04.Aug.2024 – Last update:
14. Sep. 2026