

Containing :
VTM terminal tables (Standard)

Directory Name :
210455G03-XX-01S

User Name : FLOPPY-USER

[illegible]

ND SOFTWARE LIBRARY DISKETTE

Directory Name :
210455G03-XX-02S

[illegible]

ND SOFTWARE LIBRARY DISKETTE

PAGE 1

Containing :
VTM terminal tables (Standard)

Directory Name :
210455G03-XX-03S

User Name : FLOPPY-USER

No	File name	Type T	Public	Friend	Own	Pages	Bytes
0	VTM-COMPOUND-G03	PROG C	R	RWACD	RWACD	124	253952
1	VTM-ARRAYS-E08	NRF C	R	RWACD	RWACD	20	40732
2	files using 144 pages.						148 pages reserved out of 148 pages.

ND SOFTWARE LIBRARY DISKETTE

PAGE 1

Containing :
VTM terminal tables (Standard)

Directory Name :
210455G03-XX-04S

User Name : FLOPPY-USER

No	File name	Type	T	Public	Friend	Own	Pages	Bytes
0	VTM-1B-ARRAY-E08	BRF	C	R	RWACD	RWACD	17	32977
1	VTM-2B-ARRAY-E08	BRF	C	R	RWACD	RWACD	17	32979
2	VTM-ARRAYS-G03	NRF	C	R	RWACD	RWACD	46	94164
3	DDB080-7S	VTM	C	R	RWACD	RWACD	2	2170
4	DDB003-0	VTM	C	R	RWACD	RWACD	1	636
5	DDB011-0	VTM	C	R	RWACD	RWACD	1	606
6	DDB036-0	VTM	C	R	RWACD	RWACD	1	952
7	DDB052-0	VTM	C	R	RWACD	RWACD	1	1042
8	DDB053-7S	VTM	C	R	RWACD	RWACD	2	2064
9	DDB057-7S	VTM	C	R	RWACD	RWACD	2	1135
10	DDB079-0	VTM	C	R	RWACD	RWACD	1	1148
11	DDB083-7S	VTM	C	R	RWACD	RWACD	2	2082
12	DDB093-7B	VTM	C	R	RWACD	RWACD	2	3730
13	DDB091-7S	VTM	C	R	RWACD	RWACD	2	2194
14	DDB092-7S	VTM	C	R	RWACD	RWACD	2	2194
15	DDB100-7B	VTM	C	R	RWACD	RWACD	2	3690
16	DDB099-7S	VTM	C	R	RWACD	RWACD	2	1572
17	DDB100-8B	VTM	C	R	RWACD	RWACD	2	3666
18	DDB103-8B	VTM	C	R	RWACD	RWACD	2	3542
19	DDB110-7B	VTM	C	R	RWACD	RWACD	2	3762
20	DDB105-7S	VTM	C	R	RWACD	RWACD	2	2002
21	DDB113-7B	VTM	C	R	RWACD	RWACD	2	3732
22	DDB090-7B	VTM	C	R	RWACD	RWACD	2	3686
23	DDB002-0	VTM	C	R	RWACD	RWACD	1	606
24	DDB090-0	VTM	C	R	RWACD	RWACD	1	1891
25	DDB093-0	VTM	C	R	RWACD	RWACD	1	1639
26	DDB103-0	VTM	C	R	RWACD	RWACD	1	1736
27	DDB113-0	VTM	C	R	RWACD	RWACD	1	1820
28	DDB110-0	VTM	C	R	RWACD	RWACD	1	1764
29	DDB053-0	VTM	C	R	RWACD	RWACD	1	1488

CONTINUED

WD SOFTWARE LIBRARY DISKETTE

PAGE 2

Containing :
VTM terminal tables (Standard)

Directory Name :
210455G03-XX-04S

User Name : FLOPPY-USER

No	File name	Type	T	Public	Friend	Own	Pages	Bytes
30	DDB113-7S	VTM	C	R	RWACD	RWACD	2	1972
31	DDB057-0	VTM	C	R	RWACD	RWACD	1	1101
32	DDB080-0	VTM	C	R	RWACD	RWACD	1	1671
33	DDB083-0	VTM	C	R	RWACD	RWACD	1	1465
34	DDB090-7S	VTM	C	R	RWACD	RWACD	2	2200
35	DDB090-N	VTM	C	R	RWACD	RWACD	2	2200
36	DDB091-0	VTM	C	R	RWACD	RWACD	1	1727
37	DDB092-0	VTM	C	R	RWACD	RWACD	1	1727
38	DDB093-7S	VTM	C	R	RWACD	RWACD	2	2138
39	DDB093-N	VTM	C	R	RWACD	RWACD	2	2088
40	DDB099-0	VTM	C	R	RWACD	RWACD	1	1232
41	DDB100-7S	VTM	C	R	RWACD	RWACD	2	2194
42	DDB103-7B	VTM	C	R	RWACD	RWACD	2	3736
43	DDB100-8S	VTM	C	R	RWACD	RWACD	2	2198
44	DDB100-0	VTM	C	R	RWACD	RWACD	1	1896

45 files using 145 pages. 148 pages reserved out of 148 pages.

ND SOFTWARE LIBRARY--DISKETTE

PAGE 1

Containing :
VTM terminal tables (Standard)

Directory Name :
210455G03-XX-05S

User Name : FLOPPY-USER

No	File name	Type	T	Public	Friend	Own	Pages	Bytes
0	DDB103-7S	VTM	C	R	RWACD	RWACD	2	2138
1	DDB106-7B	VTM	C	R	RWACD	RWACD	2	3932
2	DDB103-8S	VTM	C	R	RWACD	RWACD	2	2014
3	DDB103-N	VTM	C	R	RWACD	RWACD	2	2098
4	DDB105-0	VTM	C	R	RWACD	RWACD	1	1461
5	DDB106-7S	VTM	C	R	RWACD	RWACD	2	2068
6	DDB106-0	VTM	C	R	RWACD	RWACD	1	1740
7	DDB110-7S	VTM	C	R	RWACD	RWACD	2	2198
8	DDB110-N	VTM	C	R	RWACD	RWACD	2	2186
9	DDB113-N	VTM	C	R	RWACD	RWACD	2	2148
10	DDB106-N	VTM	C	R	RWACD	RWACD	2	1756
11	DDB100-N	VTM	C	R	RWACD	RWACD	2	2046

12 files using 22 pages. 148 pages reserved out of 148 pages.

ND. SOFTWARE LIBRARY DISKETTE

PAGE 1

Containing :
VTM terminal tables (Standard)

Directory Name :
210455G03-XX-01D

User Name : FLOPPY-USER

No	File name	Type	T	Public	Friend	Own	Pages	Bytes
0	VTM-COMPOUND-G03	PROG	C	R	RWACD	RWACD	124	253952
1	VTM-COMPOUND-E08	PROG	C	R	RWACD	RWACD	107	219136
2	VTM-ARRAYS-E08	NRF	C	R	RWACD	RWACD	20	40732
3	VTM-ARRAYS-G03	NRF	C	R	RWACD	RWACD	46	94164
4	VTM-1B-ARRAY-G03	BRF	C	R	RWACD	RWACD	38	76230
5	VTM-1B-ARRAY-E08	BRF	C	R	RWACD	RWACD	17	32977
6	VTM-2B-ARRAY-E08	BRF	C	R	RWACD	RWACD	17	32979
7	VTM-2B-ARRAY-G03	BRF	C	R	RWACD	RWACD	38	76232
8	VTM-ALL-TYPES	VTM	C	R	RWACD	RWACD	2	3712
9	DDBTABLES-E08	VTM	C	R	RWACD	RWACD	16	32574
10	DDBTABLES-C08	VTM	C	R	RWACD	RWACD	15	30534
11	DDBTABLES-D08	VTM	C	R	RWACD	RWACD	15	30534
12	DDBTABLES-G03	VTM	C	R	RWACD	RWACD	37	75320
13	INSTALL-TABLES	PROG	C	R	RWACD	RWACD	26	53248
14	DDB080-7S	VTM	C	R	RWACD	RWACD	2	2170
15	DDB003-0	VTM	C	R	RWACD	RWACD	1	636
16	DDB011-0	VTM	C	R	RWACD	RWACD	1	606
17	DDB036-0	VTM	C	R	RWACD	RWACD	1	952
18	DDB052-0	VTM	C	R	RWACD	RWACD	1	1042
19	DDB053-7S	VTM	C	R	RWACD	RWACD	2	2064
20	DDB057-7S	VTM	C	R	RWACD	RWACD	2	1135
21	DDB079-0	VTM	C	R	RWACD	RWACD	1	1148
22	DDB083-7S	VTM	C	R	RWACD	RWACD	2	2082
23	DDB093-7B	VTM	C	R	RWACD	RWACD	2	3730
24	DDB091-7S	VTM	C	R	RWACD	RWACD	2	2194
25	DDB092-7S	VTM	C	R	RWACD	RWACD	2	2194
26	DDB100-7B	VTM	C	R	RWACD	RWACD	2	3690
27	DDB099-7S	VTM	C	R	RWACD	RWACD	2	1572
28	DDB100-8B	VTM	C	R	RWACD	RWACD	2	3666
29	DDB103-8B	VTM	C	R	RWACD	RWACD	2	3542

CONTINUED

ND SOFTWARE LIBRARY DISKETTE

PAGE 2

Containing :
VTM terminal tables (Standard)

Directory Name :
210455G03-XX-01D

User Name : FLOPPY-USER

No	File name	Type	T	Public	Friend	Own	Pages	Bytes
30	DDB110-7B	VTM	C	R	RWACD	RWACD	2	3762
31	DDB105-7S	VTM	C	R	RWACD	RWACD	2	2002
32	DDB113-7B	VTM	C	R	RWACD	RWACD	2	3732
33	DDB090-7B	VTM	C	R	RWACD	RWACD	2	3686
34	DDB002-0	VTM	C	R	RWACD	RWACD	1	606
35	DDB090-0	VTM	C	R	RWACD	RWACD	1	1891
36	DDB093-0	VTM	C	R	RWACD	RWACD	1	1639
37	DDB103-0	VTM	C	R	RWACD	RWACD	1	1736
38	DDB113-0	VTM	C	R	RWACD	RWACD	1	1820
39	DDB110-0	VTM	C	R	RWACD	RWACD	1	1764
40	DDB053-0	VTM	C	R	RWACD	RWACD	1	1488
41	DDB113-7S	VTM	C	R	RWACD	RWACD	2	1972
42	DDB057-0	VTM	C	R	RWACD	RWACD	1	1101
43	DDB080-0	VTM	C	R	RWACD	RWACD	1	1671
44	DDB083-0	VTM	C	R	RWACD	RWACD	1	1465
45	DDB090-7S	VTM	C	R	RWACD	RWACD	2	2200
46	DDB090-N	VTM	C	R	RWACD	RWACD	2	2200
47	DDB091-0	VTM	C	R	RWACD	RWACD	1	1727
48	DDB092-0	VTM	C	R	RWACD	RWACD	1	1727
49	DDB093-7S	VTM	C	R	RWACD	RWACD	2	2138
50	DDB093-N	VTM	C	R	RWACD	RWACD	2	2088
51	DDB099-0	VTM	C	R	RWACD	RWACD	1	1232
52	DDB100-7S	VTM	C	R	RWACD	RWACD	2	2194
53	DDB103-7B	VTM	C	R	RWACD	RWACD	2	3736
54	DDB100-8S	VTM	C	R	RWACD	RWACD	2	2198
55	DDB100-0	VTM	C	R	RWACD	RWACD	1	1896
56	DDB103-7S	VTM	C	R	RWACD	RWACD	2	2138
57	DDB106-7B	VTM	C	R	RWACD	RWACD	2	3932
58	DDB103-8S	VTM	C	R	RWACD	RWACD	2	2014
59	DDB103-N	VTM	C	R	RWACD	RWACD	2	2098

	CONTINUED	
--	-----------	--

ND SOFTWARE LIBRARY DISKETTE

Containing :
VTM terminal tables (Standard)

Directory Name :
210455G03-XX-01D

User Name : FLOPPY-USER

No	File name	Type	T	Public	Friend	Own	Pages	Bytes
60	DDB105-O	VTM	C	R	RWACD	RWACD	1	1461
61	DDB106-7S	VTM	C	R	RWACD	RWACD	2	2068
62	DDB106-O	VTM	C	R	RWACD	RWACD	1	1740
63	DDB110-7S	VTM	C	R	RWACD	RWACD	2	2198
64	DDB110-N	VTM	C	R	RWACD	RWACD	2	2186
65	DDB113-N	VTM	C	R	RWACD	RWACD	2	2148
66	DDB106-N	VTM	C	R	RWACD	RWACD	2	1756
67	DDB100-N	VTM	C	R	RWACD	RWACD	2	2046

68 files using 605 pages. 610 pages reserved out of 610 pages.

Date: 871127

VIM terminal tables (Standard)
210455G

Report no: 2

Program: All
Title: Revision G03 - Error correction and changes
from revision G02 and E07.

Changes from revision G02 and E07

- Now, all the DDBTABLES files are put together in one package, simplifying the installation.
- The installation program has been rewritten.
- Terminal type 106, Nokia NOTIS, is fully supported.
- "Set editing extent" is included in the VTINIT sequence of terminal types 110 and 113, Tandberg TDV 1200/1. This corrects some VTFANSI errors.
- Some errors concerning local printers on terminal type 110 and 113 have been corrected.
- Problems with numeric keypad in function mode have been solved on terminal type 110 and 113.
- The left arrow key now functions properly on terminal type 83 and 105.
- Quite a few single character bugs have been removed.
- The Program Description has been extensively rewritten.

Date 87.11.26		Norsk Data A.S PROGRAM DESCRIPTION		Page 1 of 9																															
Product	Name VTM terminal tables (Standard)		Reg. no. 210455G	Category STPR																															
Reason	New product X Change/Addition Other:		Error Correction Different Environment																																
Documentation	Title SINTRAN III Utilities Manual			ND-no. 60.151.2A																															
Purpose	Terminal description tables needed to run most full-screen programs against standard ND terminals.																																		
Prerequisites	Computer	Type	Floating format	Op. system Version																															
	100/500	All	All	SINTRAN III >= H																															
	Minimum mass storage resources for installation																																		
	User	Userspace		Number of files																															
	SYSTEM	83 pages on		4 files																															
	Minimum permanent mass storage resources																																		
	User	Userspace		Number of files																															
	SYSTEM	83 pages on		4 files																															
				ND-no. for Source 210495G																															
<table border="1"> <thead> <tr> <th>File Name</th> <th>Type</th> <th>Containing</th> </tr> </thead> <tbody> <tr> <td>DDBTABLES-C<rev></td> <td>VTM</td> <td rowspan="4">These are the new standard terminal tables to be installed on user SYSTEM by the INSTALL-TABLES program</td> </tr> <tr> <td>DDBTABLES-D<rev></td> <td>VTM</td> </tr> <tr> <td>DDBTABLES-E<rev></td> <td>VTM</td> </tr> <tr> <td>DDBTABLES-G<rev></td> <td>VTM</td> </tr> <tr> <td>INSTALL-TABLES</td> <td>PROG</td> <td>The installation program</td> </tr> <tr> <td>VTM-COMPOUND-E<rev></td> <td>PROG</td> <td>Program for creating DDBTABLES- C, D and E out of DDBxxx files</td> </tr> <tr> <td>VTM-COMPOUND-G<rev></td> <td>PROG</td> <td>Program for creating DDBTABLES- G out of DDBxxx-yz files</td> </tr> <tr> <td>VTM-ALL-TYPES</td> <td>VTM</td> <td>Terminal type names needed when running VTM-COMPOUND</td> </tr> <tr> <td>VTM-1B-ARRAY-E<rev></td> <td>BRF</td> <td>DDBTABLES-E<rev> provided as a BRF-LINKER file, needed by some programs at compilation time</td> </tr> <tr> <td>VTM-2B-ARRAY-E<rev></td> <td>BRF</td> <td>DDBTABLES-E<rev> provided as a BRF-LINKER file, needed by some programs at compilation time</td> </tr> </tbody> </table>						File Name	Type	Containing	DDBTABLES-C<rev>	VTM	These are the new standard terminal tables to be installed on user SYSTEM by the INSTALL-TABLES program	DDBTABLES-D<rev>	VTM	DDBTABLES-E<rev>	VTM	DDBTABLES-G<rev>	VTM	INSTALL-TABLES	PROG	The installation program	VTM-COMPOUND-E<rev>	PROG	Program for creating DDBTABLES- C, D and E out of DDBxxx files	VTM-COMPOUND-G<rev>	PROG	Program for creating DDBTABLES- G out of DDBxxx-yz files	VTM-ALL-TYPES	VTM	Terminal type names needed when running VTM-COMPOUND	VTM-1B-ARRAY-E<rev>	BRF	DDBTABLES-E<rev> provided as a BRF-LINKER file, needed by some programs at compilation time	VTM-2B-ARRAY-E<rev>	BRF	DDBTABLES-E<rev> provided as a BRF-LINKER file, needed by some programs at compilation time
File Name	Type	Containing																																	
DDBTABLES-C<rev>	VTM	These are the new standard terminal tables to be installed on user SYSTEM by the INSTALL-TABLES program																																	
DDBTABLES-D<rev>	VTM																																		
DDBTABLES-E<rev>	VTM																																		
DDBTABLES-G<rev>	VTM																																		
INSTALL-TABLES	PROG	The installation program																																	
VTM-COMPOUND-E<rev>	PROG	Program for creating DDBTABLES- C, D and E out of DDBxxx files																																	
VTM-COMPOUND-G<rev>	PROG	Program for creating DDBTABLES- G out of DDBxxx-yz files																																	
VTM-ALL-TYPES	VTM	Terminal type names needed when running VTM-COMPOUND																																	
VTM-1B-ARRAY-E<rev>	BRF	DDBTABLES-E<rev> provided as a BRF-LINKER file, needed by some programs at compilation time																																	
VTM-2B-ARRAY-E<rev>	BRF	DDBTABLES-E<rev> provided as a BRF-LINKER file, needed by some programs at compilation time																																	

Product	Name	Reg. no.	Category
	VTM terminal tables (Standard)	210455G	STPR

VTM-ARRAYS-E<rev>	NRF	DDBTABLES-E<rev> provided as a NRF-LINKER file, needed by some programs at compilation time
VTM-1B-ARRAY-G<rev>	BRF	DDBTABLES-G<rev> provided as a BRF-LINKER file, needed by some programs at compilation time
VTM-2B-ARRAY-G<rev>	BRF	DDBTABLES-G<rev> provided as a BRF-LINKER file, needed by some programs at compilation time
VTM-ARRAYS-G<rev>	NRF	DDBTABLES-G<rev> provided as a NRF-LINKER file, needed by some programs at compilation time
DDB002-O	VTM	Each of these DDBxxx files contain information about a corresponding terminal type, denoted by the three digits following DDB in the filenames. A numbered list of standard terminal type names is found under "INSTALLATION". The DDBxxx files are put together in tables by VTM-COMPOUND. DDBxxx-O files might be used in DDBTABLES- C, D, E and G. DDBxxx-N files fit into DDBTABLES- E and G, while DDBxxx- 7S, 7B, 8S and 8B files are usable with DDBTABLES- G only
DDB003-O	VTM	
DDB011-O	VTM	
DDB036-O	VTM	
DDB052-O	VTM	
DDB053-O	VTM	
DDB053-7S	VTM	
DDB057-O	VTM	
DDB057-7S	VTM	
DDB079-O	VTM	
DDB080-O	VTM	
DDB080-7S	VTM	
DDB083-O	VTM	
DDB083-7S	VTM	
DDB090-O	VTM	
DDB090-N	VTM	
DDB090-7S	VTM	
DDB090-7B	VTM	
DDB091-O	VTM	
DDB091-7S	VTM	
DDB092-O	VTM	
DDB092-7S	VTM	
DDB093-O	VTM	
DDB093-N	VTM	
DDB093-7S	VTM	
DDB093-7B	VTM	
DDB099-O	VTM	
DDB099-7S	VTM	
DDB100-O	VTM	
DDB100-N	VTM	
DDB100-7S	VTM	
DDB100-7B	VTM	
DDB100-8S	VTM	
DDB100-8B	VTM	
DDB103-O	VTM	Note that there will be no need for users to create own DDBTABLES, as long as they use the standard terminal types supported by Norsk Data
DDB103-N	VTM	
		See "INSTALLATION"

Date 87.11.26		Norsk Data A.S PROGRAM DESCRIPTION		Page 3 of 9	
Product	Name VTM terminal tables (Standard)	Reg. no. 210455G	Category STPR		
DDB103-7S	VTM				
DDB103-7B	VTM				
DDB103-8S	VTM				
DDB103-8B	VTM				
DDB105-O	VTM				
DDB105-7S	VTM				
DDB106-O	VTM				
DDB106-N	VTM				
DDB106-7S	VTM				
DDB106-7B	VTM				
DDB110-O	VTM				
DDB110-N	VTM				
DDB110-7S	VTM				
DDB110-7B	VTM				
DDB113-O	VTM				
DDB113-N	VTM				
DDB113-7S	VTM				
DDB113-7B	VTM				

1 NOTE:

<rev> is to be replaced by the current revision of the DIRECTORY or FILE. The revision level is found on the preceding "ND SOFTWARE LIBRARY DISKETTE" pages.

2 OVERVIEW:

Most Norsk Data full-screen programs (like NOTIS-WP) utilize what known as Virtual Terminal Manager routines (VTM). VTM provides the programs with a standard terminal interface, and uses translation tables to communicate with the different terminal types. To ease error correction, and enable new terminal types to be used with existing programs, the translation tables, DDBTABLES- C, D, E and G, are kept as separate files on user SYSTEM. This floppy diskette contains the standard DDBTABLES- C<rev>, D<rev>, E<rev> and G<rev>.

3 INSTALLATION:

If all the terminals connected to your Norsk Data computer are among the standard terminal types (see list below), the installation is a straightforward task. The table below also shows which DDBxxx files are included in the different DDBTABLES.

Product	Name VTM terminal tables (Standard)	Reg. no. 210455G	Category STPR
---------	--	---------------------	------------------

Type	Standard terminal type name	C	D	E	G	DDBTABLES
2	Teletype ASR 33	0	0	0	0	
3	Tandberg TDV 2115	0	0	0	0	
11	DEC LA36 (Decwriter II)	0	0	0	0	
36	Tandberg TDV 2215	0	0	0	0	
52	Tandberg TDV 2215 SDS V2	0	0	0	0	
53	Tandberg TDV 2200/9 ND-NOTIS	0	0	0	7S	
57	Facit 4420 ND-NOTIS	0	0	0	7S	
79	IBM PC (ND-Link)	0	0	0	0	
80	Tandberg TDV 2200/9 ND-NET	0	0	0	7S	
83	Tandberg TDV 2200/9 V2 ND-NOTIS	0	0	0	7S	
90	Tandberg TDV 2200/9S ND-NET	0	0	N	7S,7B	
91	Facit Twist ND-NOTIS (24 lines)	0	0	0	7S	
92	Facit Twist ND-NOTIS (72 lines)	0	0	0	7S	
93	Tandberg TDV 2200/9S ND-NOTIS	0	0	N	7S,7B	
99	Colortrend 210 ND-NOTIS	0	0	0	7S	
100	Tandberg TDV 2200/9S 25 ND-NET	0	0	N	7S,7B,8S,8B	
103	Tandberg TDV 2200/9S 25 ND-NOTIS	0	0	N	7S,7B,8S,8B	
105	Butterfly 110 Console ND-NOTIS	0	0	0	7S	
106	Nokia NOTIS	0	0	N	7S,7B	
110	Tandberg TDV 1200/1 ND-NET	0	0	N	7S,7B	
113	Tandberg TDV 1200/1 ND-NOTIS	0	0	N	7S,7B	

To install the standard VTM tables you must be logged on as user SYSTEM. Ensure that the existing DDBTABLES files are called "DDBTABLES-vxx:VTM", by typing:

@LIST-FILES DDBTABLES:VTM,,

"v" should be the letter C, D, E or G, while "xx" is supposed to be a revision number. If the files are named differently, rename them to "DDBTABLES-C00:VTM", "DDBTABLES-D00:VTM", "DDBTABLES-E00:VTM" and "DDBTABLES-G00:VTM".

Now insert the floppy diskette in a free slot. Note the device name and device unit of the slot, then type:

@ENTER-DIRECTORY 210455G

Answer the questions for device name and unit, before typing:

@210455G:FLOPPY-USER)INSTALL-TABLES

Note that the INSTALL-TABLES program will refuse to overwrite any files with higher revision numbers than the tables which it is supposed to install.

Date 87.11.26		Norsk Data A.S		Page 5 of 9	
PROGRAM DESCRIPTION					
Product	Name	Reg. no.	Category		
	VTM terminal tables (Standard)	210455G	STPR		

When the computer prompts "Installing finished", just remove the floppy diskette, and store it for safe keeping. Now all VTM-table dependant programs should work appropriately on your system.

If you are using standard terminal types only (listed above), there is really no need to read the rest of this program description, which is devoted to enabling users to compound their own DDBTABLES.

4 COMPOUNDING OWN TABLES:

If non-standard terminal types are to be used with ND full-screen programs, the user has to put together their own DDBTABLES from DDBxxx files, using the VTM-COMPOUND programs. Use "VTM-COMPOUND-G:PROG" to change DDBTABLES- G, but stick to "VTM-COMPOUND-E:PROG" for compounding DDBTABLES- C, D and E.

Before being able to change anything, the contents of this floppy diskette must be copied onto a user area, preferably an empty one, with at least 650 pages free space. When compounding is finished, the existing DDBTABLES- C, D, E and G on user area SYSTEM must be replaced by the newly created files. WARNING: Keep backup copies of the original files, for example by renaming them to "DDBTABLES-vxx:SAVE". Otherwise you might end up with a computer unable to run NOTIS-WP, or any other full-screen program. After a short test period to ensure the functionality of the new tables, the VTM-COMPOUND user area may be deleted.

DDBxxx-O files may be compounded into all DDBTABLES versions, while DDBxxx-N files fit into DDBTABLES- E and G. DDBxxx- 7S, 7B, 8S and 8B files are only usable with DDBTABLES-G. Note that some DDBxxx-O files formerly were called DDBxxx-C or DDBxxx-A, while a few DDBxxx-N files were named DDBxxx-E.

Be aware that VTM-COMPOUND-E expects its file names to be unambiguous or of the type "DDBxxx:VTM". Neither DDBxxx-O nor DDBxxx-N is allowed. That means you will have to rename your files before use. In the same way VTM-COMPOUND-G requires its file names to be "DDBxxx-7S:VTM", "DDBxxx-7B:VTM", "DDBxxx-8S:VTM" or "DDBxxx-8B:VTM". Files like DDBxxx, DDBxxx-O and DDBxxx-N must be renamed to "DDBxxx-7S:VTM" before they are recognized.

The table below shows which combinations are valid. As a general rule you will not receive any error message if you mix up the different versions. The DDBTABLES will merely cease working.

Product	Name VTM terminal tables (Standard)	Reg. no. 210455G	Category STPR
---------	--	---------------------	------------------

Tables	Allowed DDB-files	Compound	Allowed DDB-filenames
C	O	E	DDBxxx:VTM
D	O	E	DDBxxx:VTM
E	O,N	E	DDBxxx:VTM
G	O,N,7S,7B,8S,8B	G	DDBxxx- 7S, 7B, 8S, 8B :VTM

This floppy diskette contains all the standard DDBxxx files. More than 50 non-standard DDBxxx files may be ordered from Norsk Data, even though we recommend the use of standard terminal types.

5 USING THE COMPOUND PROGRAMS:

The VTM-COMPOUND programs are menu driven. VTM-COMPOUND-G was originally written to replace the -E version, but in its present form VTM-COMPOUND-G does not handle DDBTABLES-C, D and E properly. This program description will focus on VTM-COMPOUND-E, but running VTM-COMPOUND-G will be a quite similar experience.

The main menu of VTM-COMPOUND-E looks like this:

```

1:  GENERATE A NEW FILE
2:  ADD TERMINAL TYPES
3:  DELETE TERMINAL TYPES
4:  GENERATE A FILE WITH BRF OR NRF FORMAT
5:  LIST TERMINAL TYPES
6:  LIST    CPU-TYPE, CPU-NUMBER AND FILE VERSION NUMBER
7:  CHANGE CPU-TYPE, CPU-NUMBER AND FILE VERSION NUMBER
8:  EDIT THE CONTENTS IN DDB999:VTM
9:  EXIT

```

ANSWER: _

Unlike VTM-COMPOUND-G, the -E version crashes when it gets too many files for it to handle. If you plan to change an existing DDBTABLES-C, D or E, the first thing you must do is to delete a couple of terminal types. For example, like this:

Date 87.11.26

Norsk Data A.S
PROGRAM DESCRIPTION

Page 7 of 9

Product	Name	Reg. no.	Category
	VTM terminal tables (Standard)	210455G	STPR

Command	Comment
3	Choose to delete terminal types
2	You want to change a DDBTABLES file
C	Choose to edit DDBTABLES- C, D or E
2	Delete terminal type 2 from the chosen DDBTABLES file
11	Delete terminal type 11 as well
777	No more terminal types to delete

Note that when you delete terminal types using VTM-COMPOUND-G, you delete the -7S, 7B, 8S and 8B entries. You have to add these four separately to get them back.

To add terminal types 4 and 114 to your DDBTABLES-C file from last example, the procedure is as follows: (To perform this, the non-standard DDB files DDB004:VTM and DDB114:VTM must be present on your current user area.)

Command	Comment
2	Add terminal types to DDBTABLES-C (see previous example)
4	Include terminal type 4
114	Add terminal type 114 as well
777	No more terminal types to add
9	Exit from VTM-COMPOUND-E

In order to add terminal type 4 (7S only) and 106 (both 7S and 7B) to DDBTABLES-G, follow this example. (The files DDB004-7S:VTM, DDB106-7S:VTM and DDB106-7B:VTM must exist on your current user area.)

Note that this example uses VTM-COMPOUND-G:

Command	Comment
2	Choose to add terminal types
2	You want to change a DDBTABLES file
G	Choose to edit DDBTABLES- G
4	Add DDB004-7S:VTM to the chosen DDBTABLES file
106	Add DDB106-7S:VTM
106-7B	Add DDB106-7B:VTM as well
777	No more terminal types to add
7	Exit from VTM-COMPOUND-G

On exit from the VTM-COMPOUND programs you get an on-screen list of the available terminal types. If all your terminal types are present, and the list looks correct, you have just finished making your own DDBTABLES file.

Date 87.11.26		Norsk Data A.S PROGRAM DESCRIPTION	Page 8 of 9
Product	Name VTM terminal tables (Standard)	Reg. no. 210455G	Category STPR

If the list contains a large amount of terminal types, or some terminal type names appear twice, the generated DDBTABLES file probably functions perfectly, even though it might be a good idea to generate a new file, just to correct the names.

If you are using VTM-COMPOUND-E, and the list is completely garbage, you have tried to put too many files into a table, making the file completely useless. This means you will have to compound a new file from a working DDBTABLES, or generate a totally new one.

This example shows how to generate a new DDBTABLES file.

Command	Comment
1	Choose to generate a new file
2	You want to change a DDBTABLES file
D	Choose to edit DDBTABLES- C, D or E
	Press carriage return, CPU-type is not currently used
	Carriage return, CPU-number is not currently used
	Carriage return, file version number is not currently used
83	Include terminal type 83 in the new DDBTABLES file
93	Add terminal type 93 as well
106	Add terminal type 106
113	Include terminal type 113 too
777	No more terminal types in file
9	Exit from VTM-COMPOUND-E

Note that when using VTM-COMPOUND-G, the DDBxxx- 7B, 8S and 8B files must be added specifically. Default is DDBxxx-7S only.

Another feature of the VTM-COMPOUND programs is the ability to create BRF and NRF linker files. Some programs, like VTM-COMPOUND- E and G, need to be loaded with the VTM-tables while linking.

The procedure to create linker files from DDBTABLES is as follows:

Date 87 11 26

Norsk Data A.S
PROGRAM DESCRIPTION

Page 9 of 9

Product	Name	Reg. no.	Category
	VTM terminal tables (Standard)	210455G	STPR

Command	Comment
4	Choose to generate a file with BRF or NRF format
2	The source is a DDBTABLES file
E	Choose between DDBTABLES- C, D or E
1	Generate VTM-1B-ARRAY:BRF (ND100, 1-BANK)
2	Generate VTM-2B-ARRAY:BRF (ND100, 2-BANK)
3	Generate VTM-ARRAYS:NRF (ND500)
4	Return to the main menu
9	Exit from VTM-COMPOUND-E

Please refer to the SINTRAN III Utilities Manual (ND-60.151.2A) for more details about VTM-COMPOUND-E.

