





Router: hammadullah15398

Fa 0/0 : 192.168.1.1


Se 0/1/0 : 10.10.10.2



Router: Hammadullah_15398

Fa 0/0 : 172.168.1.1

Se 0/1/0 : 20.20.20.2



Router: hammad_ullah_15398

Fa 0/0 : 191.168.1.1

Se 0/1/0 : 30.30.30.2

Router: Hammad_Ullah_15398

Fa 0/0 : 128.168.1.1

Se 0/1/0 : 40.40.40.2

hammad_ullah_15398

Physical Config CLI

IOS Command Line Interface

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#no ip address
Router(config-if)#ip address 191.14.1.1 255.255.0.0
Router(config-if)#no ip address
Router(config-if)#ip address 191.168.1.1 255.255.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#iphostname Hammadullah_15398
Hammadullah_15398(config)#ip DHCP excluded-address 191.168.1.1 191.168.1.10
Hammadullah_15398(config)#ip DHCP POOL hammadullah15398
Hammadullah_15398(dhcp-config)#network 191.168.1.0 255.255.0.0
Hammadullah_15398(dhcp-config)#default-router 191.168.1.1
Hammadullah_15398(dhcp-config)#exit
Hammadullah_15398(config)#exit
Hammadullah_15398#
%SYS-5-CONFIG_I: Configured from console by console
```

Hammad_Ullah_15398

Physical Config CLI

IOS Command Line Interface

```
Press RETURN to get started!

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#ip address 128.168.1.1 255.255.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#hostname Hammadullah_15398
Hammadullah_15398(config)#ip DHCP excluded-address 128.168.1.1 128.168.1.10
Hammadullah_15398(config)#ip DHCP POOL hammadullah15398
Hammadullah_15398(dhcp-config)#network 128.168.1.0 255.255.0.0
Hammadullah_15398(dhcp-config)#default-router 128.168.1.1
Hammadullah_15398(dhcp-config)#exit
Hammadullah_15398(config)#exit
Hammadullah_15398#
%SYS-5-CONFIG_I: Configured from console by console
```


Router: hammadUllah15398

Se 0/0/0 : 30.30.30.1

Se 0/0/1 : 40.40.40.1

Se 0/1/0 : 10.10.10.1


Se 0/1/1 : 20.20.20.1




Note: This is main router where all other four routers are connected.

PC0 to PC4(Connected to hammadullah15398)

PC0:



PC1:



Note: From PC0 to PC4 all are connected to one router named as “hammadullah15398”.

PC2: from DHCP ip is 192.168.1.13


PC3: From DHCP IP is 192.168.1.14

PC4: From DHCP IP is 192.168.1.15


Checked by me

PC5 to PC9(Connected to hammadullah_15398)

PC5:



PC7:



Note: From PC5 to PC9 all are connected to one router named as “hammadullah_15398”.

PC6: from DHCP ip is 172.168.0.3


PC8: From DHCP IP is 172.168.0.4

PC9: From DHCP IP is 172.168.0.5


Checked by me

PC10 to PC14(Connected to hammad_ullah_15398)

PC10:



PC11:



Note: From PC10 to PC14 all are connected to one router named as “hammadullah_15398”.

PC12: from DHCP ip is 191.168.0.3


PC13: From DHCP IP is 191.168.0.4

PC14: From DHCP IP is 191.168.0.5


Checked by me

PC15 to PC14(Connected to Hammad_Ullah_15398)

PC15:



PC16:



Note: From PC10 to PC14 all are connected to one router named as "Hammad_Ullah_15398".

PC17: from DHCP ip is 128.168.0.3

PC18: From DHCP IP is 128.168.0.4

PC19: From DHCP IP is 128.168.0.5

Checked by me

