## **RPG Maker MV Keycodes Reference**

This document provides a reference for RPG Maker MV keyboard and gamepad keycodes, useful for input handling and plugin development.

## **Keyboard Keycodes**

| Key         | KeyCode |
|-------------|---------|
| Backspace   | 8       |
| Tab         | 9       |
| Enter       | 13      |
| Shift       | 16      |
| Ctrl        | 17      |
| Alt         | 18      |
| Pause/Break | 19      |
| CapsLock    | 20      |
| Escape      | 27      |
| Space       | 32      |
| PageUp      | 33      |
| PageDown    | 34      |
| End         | 35      |
| Home        | 36      |
| Left Arrow  | 37      |
| Up Arrow    | 38      |
| Right Arrow | 39      |
| Down Arrow  | 40      |
| Insert      | 45      |
| Delete      | 46      |
| 0           | 48      |
| 1           | 49      |
| 2           | 50      |
| 3           | 51      |
| 4           | 52      |
| 5           | 53      |
| 6           | 54      |
| 7           | 55      |
| 8           | 56      |
| 9           | 57      |
| А           | 65      |
| В           | 66      |
| С           | 67      |
| D           | 68      |
| Е           | 69      |
| F           | 70      |

|      | 74  |
|------|-----|
| G    | 71  |
| H    | 72  |
| l    | 73  |
| J    | 74  |
| K    | 75  |
| L    | 76  |
| M    | 77  |
| N    | 78  |
| 0    | 79  |
| Р    | 80  |
| Q    | 81  |
| R    | 82  |
| S    | 83  |
| Т    | 84  |
| U    | 85  |
| V    | 86  |
| W    | 87  |
| X    | 88  |
| Υ    | 89  |
| Z    | 90  |
| Num0 | 96  |
| Num1 | 97  |
| Num2 | 98  |
| Num3 | 99  |
| Num4 | 100 |
| Num5 | 101 |
| Num6 | 102 |
| Num7 | 103 |
| Num8 | 104 |
| Num9 | 105 |
| F1   | 112 |
| F2   | 113 |
| F3   | 114 |
| F4   | 115 |
| F5   | 116 |
| F6   | 117 |
| F7   | 118 |
| F8   | 119 |
| F9   | 120 |
| F10  | 121 |
| F11  | 122 |
| F12  | 123 |
| 1 12 | 120 |

## **Gamepad Button Codes**

| Button                  | Code |
|-------------------------|------|
| Button 0 (A / Cross)    | 0    |
| Button 1 (B / Circle)   | 1    |
| Button 2 (X / Square)   | 2    |
| Button 3 (Y / Triangle) | 3    |
| Left Bumper             | 4    |
| Right Bumper            | 5    |
| Left Trigger            | 6    |
| Right Trigger           | 7    |
| Back / Select           | 8    |
| Start                   | 9    |
| Left Stick Press        | 10   |
| Right Stick Press       | 11   |
| D-Pad Up                | 12   |
| D-Pad Down              | 13   |
| D-Pad Left              | 14   |
| D-Pad Right             | 15   |