


1) Log in to your home Wi-Fi router's admin panel using its default IP address (usually 192.168.0.1 or 192.168.1.1) and take a screenshot of the login page.

Hint: If you don't know your router's IP, open Command Prompt and run 'ipconfig' — look for 'Default Gateway'.




2) Find and note down the current IP address, subnet mask, and default gateway assigned to your laptop or mobile device when connected to your Wi-Fi network.


My Current IP Address: - 192.168.1.17

Subnet Mask: - 255.255.255.0

Default Gateway: - 192.168.1.1



3) Change your device's IP address from 'Obtain IP automatically' (DHCP) to a static IP in the same range as your router (for example, set it to 192.168.1.50 if your router is 192.168.1.1), and test if you still have internet access.
Constraint: Remember to revert to automatic/DHCP after testing to avoid network issues.



```
C:\Users\ITCPL>ping 192.168.1.50

Pinging 192.168.1.50 with 32 bytes of data:
Reply from 192.168.1.50: bytes=32 time<1ms TTL=128
Reply from 192.168.1.50: bytes=32 time<1ms TTL=128
Reply from 192.168.1.50: bytes=32 time<1ms TTL=128
Reply from 192.168.1.50: bytes=32 time<1ms TTL=128

Ping statistics for 192.168.1.50:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\Users\ITCPL>ping 1.1.1.1.
Ping request could not find host 1.1.1.1.. Please check the name and try again.

C:\Users\ITCPL>ping 1.1.1.1

Pinging 1.1.1.1 with 32 bytes of data:
Reply from 1.1.1.1: bytes=32 time=3ms TTL=59
Reply from 1.1.1.1: bytes=32 time=3ms TTL=59
Reply from 1.1.1.1: bytes=32 time=4ms TTL=59
Reply from 1.1.1.1: bytes=32 time=4ms TTL=59

Ping statistics for 1.1.1.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 3ms, Maximum = 4ms, Average = 3ms

C:\Users\ITCPL>
```