

## **Basic Windows Command**

#### **Basic Windows Command**

#### Network Commands

Command	Description
ipconfig	Displays IP address, subnet mask, and default gateway.
ipconfig /all	Shows detailed network configuration (MAC, DNS, DHCP, etc.).
ipconfig /all   findstr IPv4	Filters to show only IPv4 addresses.
getmac /v	Displays MAC addresses of all network interfaces with additional info.
net share	Lists shared resources on the local system.

#### User & System Identity

Command	Description
net user	Lists all local user accounts.
hostname	Shows the system's network name.
whoami	Displays the current logged-in user.

## System Utilities (Run via Win + R or Command Prompt)

Command	Description
ncpa.cpl	Opens Network Connections window.
firewall.cpl	Opens Windows Firewall settings.
appwiz.cpl	Opens Programs and Features (uninstall programs).
sysdm.cpl	Opens System Properties.

Basic Windows Command

optionalfeatures	Opens Windows Features dialog (enable/disable features).
lusrmgr.msc	Opens Local Users and Groups Manager (Not in Home edition).

#### **ILICENSING & Version**

Command	Description
winver	Shows Windows version and build number.
slmgr /xpr	Displays Windows activation status (expiration info).

# netstat – Network Statistics

Command	Description
netstat	Lists active TCP connections.
netstat -a	Shows all connections and listening ports.
netstat -n	Displays addresses and ports in numeric form.
netstat -an	Combines -a and -n to show all active/listening ports in numeric format.
netstat -b	Shows which executable created each connection (requires admin).
netstat -o	Displays the Process ID (PID) using each connection.
netstat -ano	Full details: all connections, numeric, with PID (commonly used in troubleshooting).

## telnet - Remote Connectivity Tool

Command	Description
telnet [host] [port]	Attempts to connect to a specific host and port (e.g., telnet 192.168.1.1 80).
telnet	Launches Telnet interactive prompt (if installed).

#### ! Note:

Telnet is not installed by default on modern Windows systems.

Basic Windows Command

#### To install it:

dism /online /Enable-Feature /FeatureName:TelnetClient

Basic Windows Command 3