Common Commands:

```
run      --Create and run a new container from an image
exec     --Execute a command in a running container
ps       --List containers
build    --Build an image from a Dockerfile
bake     --Build from a file
pull     --Download an image from a registry
push     --Upload an image to a registry
images   --List images
login    --Authenticate to a registry
logout   --Log out from a registry
search   --Search Docker Hub for images
version  --Show the Docker version information
info     --Display system-wide information
```

Management Commands:

```
builder    --Manage builds
buildx\*    --Docker Buildx
compose\*   --Docker Compose
container  --Manage containers
context    --Manage contexts
```

```
image      --Manage images

manifest   --Manage Docker image manifests and manifest lists

network    --Manage networks

plugin     --Manage plugins

system     --Manage Docker

trust      --Manage trust on Docker images

volume     --Manage volumes
```

Commands:

```
attach     --Attach local standard input, output, and error streams to a
running container

commit     --Create a new image from a container's changes

cp         --Copy files/folders between a container and the local filesystem

create     --Create a new container

diff       --Inspect changes to files or directories on a container's
filesystem

events     --Get real time events from the server

export     --Export a container's filesystem as a tar archive

history    --Show the history of an image

import     --Import the contents from a tarball to create a filesystem image

inspect    --Return low-level information on Docker objects

kill       --Kill one or more running containers

load       --Load an image from a tar archive or STDIN
```

```
logs       --Fetch the logs of a container

pause      --Pause all processes within one or more containers

port       --List port mappings or a specific mapping for the container

rename     --Rename a container

restart    --Restart one or more containers

rm         --Remove one or more containers

rmi        --Remove one or more images

save       --Save one or more images to a tar archive (streamed to STDOUT by
default)

start      --Start one or more stopped containers

stats      --Display a live stream of container (s) resource usage statistics

stop       --Stop one or more running containers

tag        --Create a tag TARGET\_IMAGE that refers to SOURCE\_IMAGE

top        --Display the running processes of a container

unpause    --Unpause all processes within one or more containers

update     --Update configuration of one or more containers

wait       --Block until one or more containers stop, then print their exit
codes









### **Global Options:**



--config string
```

```
Location of client config files (default "/root/snap/docker/3377/.docker")

-c, --context string

Name of the context to use to connect to the daemon (overrides DOCKER HOST

env var and default context set with "docker context use")

-D, --debug

Enable debug mode

-H, --host string

Daemon socket to connect to

-1, --log-level string

--tls

Set the logging level ("debug", "info", "warn", "error", "fatal") (default
"info")

--tlscacert string

Use TLS; implied by tlsverify

Trust certs signed only by this CA (default
"/root/snap/docker/3377/.docker/ca.pem")

--tlscert string

Path to TLS certificate file (default
"/root/snap/docker/3377/.docker/cert.pem")

--tlskey string

Path to TLS key file (default "/root/snap/docker/3377/.docker/key.pem")

--tlsverify

Use TLS and verify the remote

-v, --version

Print version information and quit

Run 'docker COMMAND --help' for more information on a command.
```