

Program 1:

```
Boot failed: not a bootable disk

Booting from Floppy...
Boot failed: could not read the boot disk

Booting from DVD/CD...
Boot failed: Could not read from CDROM (code 0003)
Booting from ROM...
iPXE (PCI 00:03.0) starting execution...ok
iPXE initialising devices...ok


iPXE 1.20.1+ (g4bd0) -- Open Source Network Boot Firmware -- http://ipxe.org
Features: DNS HTTP iSCSI TFTP AoE ELF MBOOT PXE bzImage Menu PXEXT

net0: 52:54:00:12:34:56 using 82540em on 0000:00:03.0 (open)
  ILink:up, TX:0 TXE:0 RX:0 RXE:01
Configuring (net0 52:54:00:12:34:56)..... ok
net0: 10.0.2.15/255.255.255.0 gw 10.0.2.2
Nothing to boot: No such file or directory (http://ipxe.org/2d03e13b)
No more network devices

No bootable device.
-
```

Program 2:

```
SeaBIOS (version rel-1.17.0-0-gb52ca86e094d-prebuilt.qemu.org)

iPXE (http://ipxe.org) 00:03.0 CA00 PCI2.10 PnP PMM+06FD1FB0+06F31FB0 CA00

Booting from Hard Disk...
```

Commands run

```
[hawk@nixos:/run/media/hawk/D-drive/Fox/Cs744/lab1/task5]$ nasm boot_sector1.asm -f bin -o boot_sector1.bin
[hawk@nixos:/run/media/hawk/D-drive/Fox/Cs744/lab1/task5]$ od -t x1 -A n boot_sector1.bin
eb fe 00 00 00 00 00 00 00 00 00 00 00 00 00
00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
*
00 00 00 00 00 00 00 00 00 00 00 00 00 00 00

[hawk@nixos:/run/media/hawk/D-drive/Fox/Cs744/lab1/task5]$ nasm boot_sector2.asm -f bin -o boot_sector2.bin
[hawk@nixos:/run/media/hawk/D-drive/Fox/Cs744/lab1/task5]$ od -t x1 -A n boot_sector2.bin
eb fe 00 00 00 00 00 00 00 00 00 00 00 00 00
00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
*
00 00 00 00 00 00 00 00 00 00 00 00 00 00 55 aa

[hawk@nixos:/run/media/hawk/D-drive/Fox/Cs744/lab1/task5]$ qemu-system-i386 boot_sector1.bin
WARNING: Image format was not specified for 'boot_sector1.bin' and probing guessed raw.
        Automatically detecting the format is dangerous for raw images, write operations on block 0 will be restricted.
        Specify the 'raw' format explicitly to remove the restrictions.

^Cqemu: terminating on signal 2

[hawk@nixos:/run/media/hawk/D-drive/Fox/Cs744/lab1/task5]$ qemu-system-i386 boot_sector2.bin
WARNING: Image format was not specified for 'boot_sector2.bin' and probing guessed raw.
        Automatically detecting the format is dangerous for raw images, write operations on block 0 will be restricted.
        Specify the 'raw' format explicitly to remove the restrictions.

[hawk@nixos:/run/media/hawk/D-drive/Fox/Cs744/lab1/task5]$ qemu-system-i386 boot_sector2.bin
WARNING: Image format was not specified for 'boot_sector2.bin' and probing guessed raw.
        Automatically detecting the format is dangerous for raw images, write operations on block 0 will be restricted.
        Specify the 'raw' format explicitly to remove the restrictions.

[hawk@nixos:/run/media/hawk/D-drive/Fox/Cs744/lab1/task5]$ qemu-system-i386 boot_sector2.bin
WARNING: Image format was not specified for 'boot_sector2.bin' and probing guessed raw.
        Automatically detecting the format is dangerous for raw images, write operations on block 0 will be restricted.
        Specify the 'raw' format explicitly to remove the restrictions.
```

Ok so both have just a loop doing nothing.

However the first one doesn't even have a driver defined so it fails.

The second has one so it just gets stuck in the loop.